



Nextcloud Server Administration Manual

Release latest

The Nextcloud developers

May 02, 2022

CONTENTS

1	Introduction	1
1.1	Videos and blogs	1
1.2	Target audience	1
2	Release notes	3
3	Maintenance and release schedule	5
3.1	Major releases	5
3.2	Maintenance releases	5
3.3	Older versions	6
4	Installation and server configuration	7
4.1	System requirements	7
4.2	Deployment recommendations	9
4.3	Installation on Linux	9
4.4	Installation wizard	17
4.5	Installing from command line	21
4.6	Supported apps	22
4.7	SELinux configuration	24
4.8	NGINX configuration	27
4.9	Hardening and security guidance	35
4.10	Server tuning	40
4.11	Example installation on Ubuntu 20.04 LTS	42
4.12	Example installation on CentOS 8	44
5	Nextcloud configuration	49
5.1	Warnings on admin page	49
5.2	Using the occ command	51
5.3	Activity app	77
5.4	Memory caching	78
5.5	Background jobs	82
5.6	Configuration Parameters	85
5.7	Email	115
5.8	Linking external sites	122
5.9	Language & Locale	125
5.10	Logging	126
5.11	Antivirus scanner	128
5.12	Reverse proxy	133
5.13	Brute force protection	136
5.14	Automatic setup	136

5.15	Theming	138
5.16	OAuth2	141
6	Apps management	143
6.1	Apps	143
6.2	Managing apps	144
6.3	Using private API	145
6.4	Using custom app directories	145
6.5	Using a self hosted apps store	145
7	User management	147
7.1	User management	147
7.2	Resetting a lost admin password	152
7.3	Resetting a user password	153
7.4	User password policy	153
7.5	Two-factor authentication	154
7.6	User authentication with IMAP, SMB, FTP and others	156
7.7	User authentication with LDAP	156
7.8	LDAP user cleanup	172
7.9	The LDAP configuration API	174
7.10	User provisioning API	179
8	File sharing and management	199
8.1	File Sharing	199
8.2	Configuring Federation Sharing	203
8.3	Uploading big files > 512MB	208
8.4	Providing default files	211
8.5	Configuring Object Storage as Primary Storage	213
8.6	Configuring External Storage (GUI)	216
8.7	External Storage authentication mechanisms	228
8.8	Encryption configuration	229
8.9	Encryption details	237
8.10	Encryption migration	246
8.11	Transactional file locking	246
8.12	Previews configuration	248
8.13	Controlling file versions and aging	249
9	File workflows	251
9.1	Files access control	251
9.2	Automated tagging of files	254
9.3	Retention of files	255
10	Groupware	257
10.1	Calendar	257
11	Database configuration	259
11.1	Converting database type	259
11.2	Database configuration	260
11.3	Enabling MySQL 4-byte support	267
11.4	BigInt (64bit) identifiers	268
12	Mimetypes management	269
12.1	Mimetype aliases	269
12.2	Mimetype mapping	269
12.3	Icon retrieval	270

13 Maintenance	271
13.1 Backup	271
13.2 Restoring backup	272
13.3 How to upgrade	274
13.4 Upgrade via built-in updater	276
13.5 Upgrade manually	290
13.6 Upgrade via packages	292
13.7 Migrating to a different server	294
13.8 Migrating from ownCloud	295
14 Issues and troubleshooting	297
14.1 General troubleshooting	297
14.2 Code signing	303
15 GDPR	309
15.1 Cookies	309

INTRODUCTION

Welcome to the Nextcloud Server Administration Guide. This guide describes administration tasks for Nextcloud, the flexible open source file synchronization and sharing solution. Nextcloud includes the Nextcloud server, which runs on Linux, client applications for Microsoft Windows, macOS and Linux, and mobile clients for the Android and Apple iOS operating systems.

Current editions of Nextcloud manuals are always available online at docs.nextcloud.com.

Nextcloud server is available:

- As a free, full featured community-supported server, with all enterprise features.
- Or with full enterprise support, including phone and email access to Nextcloud developers.

1.1 Videos and blogs

See the [official Nextcloud channel](#) on YouTube for tutorials, overviews, and conference videos.

Visit [Nextcloud Planet](#) for news and developer blogs.

1.2 Target audience

This guide is for users who want to install, administer, and optimize their Nextcloud servers. To learn more about the Nextcloud Web user interface, and desktop and mobile clients, please refer to their respective manuals:

- [Nextcloud User Manual](#)
- [Nextcloud Desktop Client](#)

RELEASE NOTES

See [the official changelog](#) for release notes.

MAINTENANCE AND RELEASE SCHEDULE

This page gives an overview of the currently supported and released versions as well as basic release scheduling.

	release date	end of life
21	2021-02-22	2022-02
20	2020-10-03	2021-10
19	2020-06-03	2021-06

Find the detailed schedule for major and maintenance releases at: [GitHub](#).

3.1 Major releases

Major releases are typically scheduled once every 4 months with the first 10 weeks being the development phase followed by freeze phase with four beta release, two RCs and one final each one with an interval of 1 week. Specific dates for each release can be found on [GitHub](#).

Major releases are planned to be actively maintained for at least 8 months after their release. For long term support options check out the [Nextcloud Subscription](#) offered by [Nextcloud GmbH](#).

3.2 Maintenance releases

Maintenance releases are scheduled in a 6 week cycle with one week before the release date having the freeze and RC 1.

3.3 Older versions

	release date	end of life	latest version
18	2020-01-16	2021-01	18.0.14 (2021-01-27)
17	2019-09-30	2020-10	17.0.10 (2020-10-08)
16	2019-04-25	2020-06	16.0.11 (2020-06-04)
15	2018-12-10	2019-12	15.0.14 (2019-12-19)
14	2018-09-10	2019-09	14.0.14 (2019-08-15)
13	2018-02-06	2019-02	13.0.12 (2019-02-28)
12	2017-05-22	2018-11	12.0.13 (2018-11-22)
11	2016-12-13	2018-03	11.0.8 (2018-03-15)
10	2016-08-25	2017-08	10.0.6 (2017-08-07)
9.0	2016-03-08	2017-10	9.0.58 (2017-04-24)
8.2	2015-10-20	2017-05	8.2.11 (2017-04-18)
8.1	2015-07-07	2017-02	8.1.12 (2017-02-02)
8.0	2015-02-09	2016-10	8.0.16 (2016-11-08)
7.0	2014-06-23	2016-05	7.0.15 (2016-05-12)
6.0	2013-12-11	2015-09	6.0.9 (2015-07-07)
5.0	2013-03-14	2015-03	5.0.19 (2015-03-11)
4.5	2012-10-10	2013-07	4.5.13 (2013-07-10)
4.0	2012-05-22	2013-07	4.0.16 (2013-07-06)
3.0	2012-01-31	2012-04	3.0.3 (2012-04-27)
2.0	2011-10-11	2012-01	
1.0	2010-06-24	2011-10	

INSTALLATION AND SERVER CONFIGURATION

4.1 System requirements

4.1.1 Server

For best performance, stability and functionality we have documented some recommendations for running a Nextcloud server.

Note: If you plan a setup for your organization and you rely on professional deployment consulting (e.g. efficient and reliable scaling) and support, we strongly recommend you to check out our [enterprise support](#).

Platform	Options
Operating System	• Ubuntu 20.04 LTS (recommended) • Red Hat Enterprise Linux 8 (recommended) • Debian 10 (Buster) • SUSE Linux Enterprise Server 15 • openSUSE Leap 42.1+ • CentOS 8
Database	• MySQL 8.0+ or MariaDB 10.2/10.3/10.4/10.5 (recommended) • Oracle Database 11g (<i>only as part of an enterprise subscription</i>) • PostgreSQL 9.6/10/11/12/13 • SQLite (<i>only recommended for testing and minimal-instances</i>)
Webserver	• Apache 2.4 with mod_php or php-fpm (recommended) • nginx with php-fpm
PHP Runtime	• 7.3 • 7.4 • 8.0 (<i>recommended</i>)

See *Installation on Linux* for minimum PHP-modules and additional software for installing Nextcloud.

Memory

Memory requirements for running a Nextcloud server are greatly variable, depending on the numbers of users, apps, files and volume of server activity.

Nextcloud needs a minimum of **128MB** RAM, and we recommend a minimum of **512MB**.

Database requirements for MySQL / MariaDB

The following is currently required if you're running Nextcloud together with a MySQL / MariaDB database:

- InnoDB storage engine (MyISAM is not supported)
- “READ COMMITTED” transaction isolation level (See: *Database “READ COMMITTED” transaction isolation level*)
- Disabled or BINLOG_FORMAT = ROW configured Binary Logging (See: <https://dev.mysql.com/doc/refman/5.7/en/binary-log-formats.html>)
- For **Emoji (UTF8 4-byte) support** see *Enabling MySQL 4-byte support*

4.1.2 Desktop client

We strongly recommend using the latest version of your operating system to get the full and most stable experience out of our clients.

- **Windows** 7+
- **macOS** Lion (10.7)+ (64-bit only)
- **Linux** (CentOS 6.5+, Ubuntu 14.04+, Fedora 21+, openSUSE 13, SUSE Linux Enterprise 11 SP3+, Debian 8 (Jessie)+, Red Hat Enterprise Linux 7)

4.1.3 Mobile apps

We strongly recommend using the latest version of your mobile operating system to get the full and most stable experience out of our mobile apps.

- **iOS** 11.x+
- **Android** 4.x+

Note: The separate Nextcloud Talk app requires iOS 10.x+ or Android 5.x+.

4.1.4 Web browser

For the best experience with the Nextcloud web interface, we recommend that you use the latest and supported version of a browser from this list, or one based on those:

- Microsoft **Internet Explorer 11** (latest version)
- Microsoft **Edge**
- Mozilla **Firefox**
- Google **Chrome**/Chromium
- Apple **Safari**

Note: If you want to use Nextcloud Talk you should use Mozilla **Firefox** 52+ or Google **Chrome**/Chromium 49+ to have the full experience with video calls and screensharing. Google Chrome/Chromium requires an additional plugin for screensharing.

4.2 Deployment recommendations

Find up-to-date deployment recommendations for enterprises in our [customer portal](#).

4.3 Installation on Linux

In case you prefer installing from the source tarball, you can setup Nextcloud from scratch using a classic LAMP stack (Linux, Apache, MySQL/MariaDB, PHP). This document provides a complete walk-through for installing Nextcloud on Ubuntu 18.04 LTS Server with Apache and MariaDB, using the [Nextcloud .tar archive](#). This method is recommended to install Nextcloud.

Note: Admins of SELinux-enabled distributions such as CentOS, Fedora, and Red Hat Enterprise Linux may need to set new rules to enable installing Nextcloud. See [SELinux configuration tips](#) for a suggested configuration.

If you prefer a more automated installation of Nextcloud and there are no packages for your Linux distribution, you have the option to install the community [Snap Package](#). This includes a full production-ready stack, will maintain your HTTPS certificates for you, and will automatically update as needed to stay secure. You can also use the [Nextcloud VM scripts](#) to install directly on a clean Ubuntu Server. It will setup everything for you and include scripts for automated installation of apps like; Collabora, OnlyOffice, Talk and so on. Please note that those two options are not officially supported by Nextcloud GmbH.

This installation guide is giving a general overview of required dependencies and their configuration. For a distribution specific setup guide have a look at the [Example installation on Ubuntu 20.04 LTS](#) and [Example installation on CentOS 8](#).

4.3.1 Prerequisites for manual installation

The Nextcloud .tar archive contains all of the required PHP modules. This section lists all required and optional PHP modules. Consult the [PHP manual](#) for more information on modules. Your Linux distribution should have packages for all required modules. You can check the presence of a module by typing `php -m | grep -i <module_name>`. If you get a result, the module is present.

Required:

- PHP (7.3 or 7.4)
- PHP module ctype
- PHP module curl
- PHP module dom
- PHP module filter (only on Mageia and FreeBSD)
- PHP module GD
- PHP module hash (only on FreeBSD)
- PHP module JSON
- PHP module libxml (Linux package libxml2 must be $\geq 2.7.0$)
- PHP module mbstring
- PHP module openssl
- PHP module posix
- PHP module session
- PHP module SimpleXML
- PHP module XMLReader
- PHP module XMLWriter
- PHP module zip
- PHP module zlib

Database connectors (pick the one for your database:)

- PHP module pdo_sqlite (≥ 3 , usually not recommended for performance reasons)
- PHP module pdo_mysql (MySQL/MariaDB)
- PHP module pdo_pgsql (PostgreSQL)

Recommended packages:

- PHP module fileinfo (highly recommended, enhances file analysis performance)
- PHP module bz2 (recommended, required for extraction of apps)
- PHP module intl (increases language translation performance and fixes sorting of non-ASCII characters)

Required for specific apps:

- PHP module ldap (for LDAP integration)
- PHP module smbclient (SMB/CIFS integration, see [SMB/CIFS](#))
- PHP module ftp (for FTP storage / external user authentication)
- PHP module imap (for external user authentication)

- PHP module bcmath (for passwordless login)
- PHP module gmp (for passwordless login)

Recommended for specific apps (*optional*):

- PHP module gmp (for SFTP storage)
- PHP module exif (for image rotation in pictures app)

For enhanced server performance (*optional*) select one of the following memcaches:

- PHP module apcu ($\geq 4.0.6$)
- PHP module memcached
- PHP module redis ($\geq 2.2.6$, required for Transactional File Locking)

See [Memory caching](#) to learn how to select and configure a memcache.

For preview generation (*optional*):

- PHP module imagick
- avconv or ffmpeg
- OpenOffice or LibreOffice

For command line processing (*optional*):

- PHP module pcntl (enables command interruption by pressing `ctrl-c`)

For command line updater (*optional*):

- PHP module phar (upgrades Nextcloud by running `sudo -u www-data php /var/www/nextcloud/updater/updater.phar`)

You don't need the WebDAV module for your Web server (i.e. Apache's `mod_webdav`), as Nextcloud has a built-in WebDAV server of its own, SabreDAV. If `mod_webdav` is enabled you must disable it for Nextcloud. (See [Apache Web server configuration](#) for an example configuration.)

4.3.2 Apache Web server configuration

Configuring Apache requires the creation of a single configuration file. On Debian, Ubuntu, and their derivatives, this file will be `/etc/apache2/sites-available/nextcloud.conf`. On Fedora, CentOS, RHEL, and similar systems, the configuration file will be `/etc/httpd/conf.d/nextcloud.conf`.

You can choose to install Nextcloud in a directory on an existing webserver, for example `https://www.example.com/nextcloud/`, or in a virtual host if you want Nextcloud to be accessible from its own subdomain such as `https://cloud.example.com/`.

To use the directory-based installation, put the following in your `nextcloud.conf` replacing the **Directory** and **Alias** filepaths with the filepaths appropriate for your system:

```
Alias /nextcloud "/var/www/nextcloud/"

<Directory /var/www/nextcloud/>
    Require all granted
    AllowOverride All
    Options FollowSymLinks MultiViews

    <IfModule mod_dav.c>
```

(continues on next page)

(continued from previous page)

```
Dav off
</IfModule>
</Directory>
```

To use the virtual host installation, put the following in your `nextcloud.conf` replacing **ServerName**, as well as the **DocumentRoot** and **Directory** filepaths with values appropriate for your system:

```
<VirtualHost *:80>
    DocumentRoot /var/www/nextcloud/
    ServerName your.server.com

    <Directory /var/www/nextcloud/>
        Require all granted
        AllowOverride All
        Options FollowSymLinks MultiViews

        <IfModule mod_dav.c>
            Dav off
        </IfModule>
    </Directory>
</VirtualHost>
```

On Debian, Ubuntu, and their derivatives, you should run the following command to enable the configuration:

```
a2ensite nextcloud.conf
```

Additional Apache configurations

- For Nextcloud to work correctly, we need the module `mod_rewrite`. Enable it by running:

```
a2enmod rewrite
```

Additional recommended modules are `mod_headers`, `mod_env`, `mod_dir` and `mod_mime`:

```
a2enmod headers
a2enmod env
a2enmod dir
a2enmod mime
```

If you're running `mod_fcgi` instead of the standard `mod_php` also enable:

```
a2enmod setenvif
```

- You must disable any server-configured authentication for Nextcloud, as it uses Basic authentication internally for DAV services. If you have turned on authentication on a parent folder (via e.g. an `AuthType Basic` directive), you can turn off the authentication specifically for the Nextcloud entry. Following the above example configuration file, add the following line in the `<Directory>` section:

```
Satisfy Any
```

- When using SSL, take special note of the `ServerName`. You should specify one in the server configuration, as well as in the `CommonName` field of the certificate. If you want your Nextcloud to be reachable via the internet, then set both of these to the domain you want to reach your Nextcloud server.

- Now restart Apache:

```
service apache2 restart
```

- If you're running Nextcloud in a subdirectory and want to use CalDAV or CardDAV clients make sure you have configured the correct *Service discovery* URLs.

4.3.3 Pretty URLs

Pretty URLs remove the `index.php`-part in all Nextcloud URLs, for example in sharing links like `https://example.org/nextcloud/index.php/s/Sv1b7krAUqmF8QQ`, making URLs shorter and thus prettier.

`mod_env` and `mod_rewrite` must be installed on your webserver and the `.htaccess` must be writable by the HTTP user. Then you can set in the `config.php` two variables:

```
'overwrite.cli.url' => 'https://example.org/nextcloud',
'htaccess.RewriteBase' => '/nextcloud',
```

if your setup is available on `https://example.org/nextcloud` or:

```
'overwrite.cli.url' => 'https://example.org/',
'htaccess.RewriteBase' => '/',
```

if it isn't installed in a subfolder. Finally run this occ-command to update your `.htaccess` file:

```
sudo -u www-data php /var/www/nextcloud/occ maintenance:update:htaccess
```

After each update, these changes are automatically applied to the `.htaccess`-file.

4.3.4 Enabling SSL

Note: You can use Nextcloud over plain HTTP, but we strongly encourage you to use SSL/TLS to encrypt all of your server traffic, and to protect user's logins and data in transit.

Apache installed under Ubuntu comes already set-up with a simple self-signed certificate. All you have to do is to enable the `ssl` module and the default site. Open a terminal and run:

```
a2enmod ssl
a2ensite default-ssl
service apache2 reload
```

Note: Self-signed certificates have their drawbacks - especially when you plan to make your Nextcloud server publicly accessible. You might want to consider getting a certificate signed by a commercial signing authority. Check with your domain name registrar or hosting service for good deals on commercial certificates.

4.3.5 Installation wizard

After restarting Apache you must complete your installation by running either the graphical Installation Wizard, or on the command line with the `occ` command. To enable this, change the ownership on your Nextcloud directories to your HTTP user:

```
chown -R www-data:www-data /var/www/nextcloud/
```

Note: Admins of SELinux-enabled distributions may need to write new SELinux rules to complete their Nextcloud installation; see [SELinux configuration tips](#).

To use `occ` see [Installing from command line](#).

To use the graphical Installation Wizard see [Installation wizard](#).

4.3.6 SELinux configuration tips

See [SELinux configuration](#) for a suggested configuration for SELinux-enabled distributions such as Fedora and CentOS.

4.3.7 php.ini configuration notes

Keep in mind that changes to `php.ini` may have to be configured on more than one ini file. This can be the case, for example, for the `date.timezone` setting.

php.ini - used by the Web server:

```
/etc/php/7.4/apache2/php.ini  
or  
/etc/php/7.4/fpm/php.ini  
or ...
```

php.ini - used by the php-cli and so by Nextcloud CRON jobs:

```
/etc/php/7.4/cli/php.ini
```

Note: Path names have to be set in respect of the installed PHP (≥ 7.3 or 7.4) as applicable.

4.3.8 php-fpm configuration notes

System environment variables

When you are using `php-fpm`, system environment variables like `PATH`, `TMP` or others are not automatically populated in the same way as when using `php-cli`. A PHP call like `getenv('PATH')`; can therefore return an empty result. So you may need to manually configure environment variables in the appropriate `php-fpm` ini/config file.

Here are some example root paths for these ini/config files:

Debian/Ubuntu/Mint	CentOS/Red Hat/Fedora
/etc/php/7.4/fpm/	/etc/php-fpm.d/

In both examples, the ini/config file is called `www.conf`, and depending on the distro version or customizations you have made, it may be in a subdirectory such as `pool.d`.

Usually, you will find some or all of the environment variables already in the file, but commented out like this:

```
;env[HOSTNAME] = $HOSTNAME
;env[PATH] = /usr/local/bin:/usr/bin:/bin
;env[TMP] = /tmp
;env[TMPDIR] = /tmp
;env[TEMP] = /tmp
```

Uncomment the appropriate existing entries. Then run `printenv PATH` to confirm your paths, for example:

```
$ printenv PATH
/home/user/bin:/usr/local/sbin:/usr/local/bin:/usr/sbin:/usr/bin:
/sbin:/bin:/
```

If any of your system environment variables are not present in the file then you must add them.

Alternatively it is possible to use the environment variables of your system by modifying:

```
/etc/php/7.4/fpm/pool.d/www.conf
```

and uncommenting the line:

```
clear_env = no
```

When you are using shared hosting or a control panel to manage your [Nextcloud VM](#) or server, the configuration files are almost certain to be located somewhere else, for security and flexibility reasons, so check your documentation for the correct locations.

Please keep in mind that it is possible to create different settings for `php-cli` and `php-fpm`, and for different domains and Web sites. The best way to check your settings is with [PHP version and information](#).

Maximum upload size

If you want to increase the maximum upload size, you will also have to modify your `php-fpm` configuration and increase the `upload_max_filesize` and `post_max_size` values. You will need to restart `php-fpm` and your HTTP server in order for these changes to be applied.

.htaccess notes for Apache

Nextcloud comes with its own `nextcloud/.htaccess` file. Because `php-fpm` can't read PHP settings in `.htaccess` these settings and permissions must be set in the `nextcloud/.user.ini` file.

4.3.9 Other Web servers

- [NGINX configuration](#)

4.3.10 Installing on Windows (virtual machine)

If you are using Windows, the easiest way to get Nextcloud up and running is using a virtual machine (VM). There are two options:

- **Enterprise/SME appliance**

Nextcloud GmbH maintains a free appliance built on the [Univention Corporate Server \(UCS\)](#) with easy graphical setup and web-based administration. It includes user management via LDAP, can replace an existing Active Directory setup and has optional ONLYOFFICE and Collabora Online integration, with many more applications available for easy and quick install.

It can be installed on hardware or run in a virtual machine using VirtualBox, VMWare (ESX) and KVM images.

Download the the Appliance here:

- [Univention Corporate Server \(UCS\)](#)
- **Home User/SME appliance**

The [Nextcloud VM](#) is maintained by [T&M Hansson IT](#) and several different versions are offered. Collabora, OnlyOffice, Full Text Search and other apps can easily be installed with the included scripts which you can choose to run during the first setup, or download them later and run it afterwards. You can find all the currently available automated app installations [on GitHub](#).

The VM comes in different sizes and versions.

You can find all the available versions [here](#).

For complete instructions and downloads see:

- [Nextcloud VM \(Github\)](#)
- [Nextcloud VM \(T&M Hansson IT\)](#)

Note: You can install the VM on several different operating systems as long as you can mount OVA, VMDK, or VHD/VHDX VM in your hypervisor. If you are using KVM then you need to install the VM from the scripts on Github. You can follow the [instructions in the README](#).

4.3.11 Installing via Snap packages

A snap is a zip file containing an application together with its dependencies, and a description of how it should safely be run on your system, especially the different ways it should talk to other software. Most importantly snaps are designed to be secure, sandboxed, containerized applications isolated from the underlying system and from other applications.

To install the Nextcloud Snap Package, run the following command in a terminal:

```
sudo snap install nextcloud
```

Note: The [snapd technology](#) is the core that powers snaps, and it offers a new way to package, distribute, update and run OS components and applications on a Linux system. See more about snaps on [snapcraft.io](#).

4.3.12 Installation via web installer on a VPS or web space

When you don't have access to the command line, for example at a web hosting or VMPS, an easy option is to use our web installer. This script can be found on our [server installation page here](#).

The script checks the dependencies, downloads Nextcloud from the official server, unpacks it with the right permissions and the right user account. Finally, you will be redirected to the Nextcloud installer. Here a quick how-to:

1. Get the file from the installation page
2. Upload setup-nextcloud.php to your web space
3. Point your web browser to setup-nextcloud.php on your webspace
4. Follow the instructions and configure Nextcloud
5. Login to your newly created Nextcloud instance!

Note: that the installer uses the same Nextcloud version as available for the built in updater in Nextcloud. After a major release it can take up to a month before it becomes available through the web installer and the updater. This is done to spread the deployment of new major releases out over time.

4.3.13 Installation via install script

One of the easiest ways of installing is to use the Nextcloud VM scripts. It's basically just two steps:

1. Download the latest [installation script](#).
2. Run the script with:

```
sudo bash nextcloud_install_production.sh
```


A guided setup will follow and the only thing you have to do it to follow the on screen instructions, when given to you.

4.4 Installation wizard

4.4.1 Quick start

When Nextcloud prerequisites are fulfilled and all Nextcloud files are installed, the last step to completing the installation is running the Installation Wizard. This is just three steps:

1. Point your Web browser to `http://localhost/nextcloud`
2. Enter your desired administrator's username and password.
3. Click **Finish Setup**.



The image shows a blue Nextcloud installation screen. At the top is the Nextcloud logo. Below it, the text 'Create an admin account' is displayed. There are two input fields: one labeled 'admin' and another labeled 'Password'. Below these fields is a dropdown menu labeled 'Storage & database' with a downward arrow. A dark blue box contains a 'Performance warning' message about SQLite. Below the warning is a checkbox labeled 'Install recommended apps' which is checked, with the text 'Calendar, Contacts, Talk, Mail & OnlyOffice' underneath. At the bottom is a large 'Finish setup' button. At the very bottom, there is a link that says 'Need help? See the documentation' with an external link icon.

Create an admin account

admin

Password

Storage & database ▾

Performance warning

You chose SQLite as database.
SQLite should only be used for minimal and development instances. For production we recommend a different database backend.
If you use clients for file syncing, the use of SQLite is highly discouraged.

☒ Install recommended apps
Calendar, Contacts, Talk, Mail & OnlyOffice

Finish setup

Need help? [See the documentation](#) ↗


You're finished and can start using your new Nextcloud server.

Of course, there is much more that you can do to set up your Nextcloud server for best performance and security. In the following sections we will cover important installation and post-installation steps.

- *Data Directory Location*
- *Database Choice*
- *Trusted Domains*

4.4.2 Data directory location

Click **Storage and Database** to expose additional installation configuration options for your Nextcloud data directory and database.



The screenshot shows the 'Storage & database' configuration screen in the Nextcloud installation wizard. The interface is blue with white text and input fields. At the top, it says 'Storage & database' with a dropdown arrow. Below that is the 'Data folder' section with a text input field containing '/var/www/nextcloud/data'. The next section is 'Configure the database', which has two tabs: 'SQLite' and 'MySQL/MariaDB'. Below the tabs are four input fields: 'Database user', 'Database password' (with an eye icon for toggling visibility), 'Database name', and 'localhost'. A note below these fields says 'Please specify the port number along with the host name (e.g., localhost:5432)'. There is a checkbox labeled 'Install recommended apps' which is checked, with the text 'Calendar, Contacts, Talk, Mail & OnlyOffice' below it. At the bottom is a large 'Finish setup' button. A link at the very bottom says 'Need help? See the documentation' with an external link icon.

You should locate your Nextcloud data directory outside of your Web root if you are using an HTTP server other than Apache, or you may wish to store your Nextcloud data in a different location for other reasons (e.g. on a storage server). It is best to configure your data directory location at installation, as it is difficult to move after installation. You may put it anywhere; in this example is it located in `/opt/nextcloud/`. This directory must already exist, and must be owned by your HTTP user.


4.4.3 Database choice

SQLite is the default database for Nextcloud Server and it is good only for testing and lightweight single-user setups without client synchronization. Supported databases are MySQL, MariaDB, Oracle 11g, and PostgreSQL, and we recommend *MySQL/MariaDB*. Your database and PHP connectors must be installed before you run the Installation Wizard. When you install Nextcloud from packages all the necessary dependencies will be satisfied (see *Installation on Linux* for a detailed listing of required and optional PHP modules). You will need the root database login, or any administrator login, and then enter any name you want for your Nextcloud database. Be careful your administrator login needs to have the permissions to create and modify databases and they need to have the permissions to grant permissions to other users.

After you enter your root or administrator login for your database, the installer creates a special database user with privileges limited to the Nextcloud database. Then Nextcloud needs only the special Nextcloud database user, and drops the root dB login. This user is named for your Nextcloud admin user, with an `oc_` prefix, and then given a random password. The Nextcloud database user and password are written into `config.php`:

```
'dbuser' => 'oc_molly',
'dbpassword' => 'pX65Ty5DrHQkYPE5HRsDvyFHlZZHcm',
```

Click Finish Setup, and start using your new Nextcloud server.




Now we will look at some important post-installation steps.

4.4.4 Trusted domains

All URLs used to access your Nextcloud server must be whitelisted in your `config.php` file, under the `trusted_domains` setting. Users are allowed to log into Nextcloud only when they point their browsers to a URL that is listed in the `trusted_domains` setting. You may use IP addresses and domain names. A typical configuration looks like this:

```
'trusted_domains' =>
array (
  0 => 'localhost',
  1 => 'server1.example.com',
  2 => '192.168.1.50',
  3 => '[fe80::1:50]',
),
```

The loopback address, `127.0.0.1`, is automatically whitelisted, so as long as you have access to the physical server you can always log in. In the event that a load balancer is in place there will be no issues as long as it sends the correct `X-Forwarded-Host` header. When a user tries a URL that is not whitelisted the following error appears:



4.5 Installing from command line

It is now possible to install Nextcloud entirely from the command line. This is convenient for scripted operations, headless servers, and sysadmins who prefer the command line. There are three stages to installing Nextcloud via the command line:

1. Download the Nextcloud code and unpack the tarball in the appropriate directories. (See [Installation on Linux](#).)
2. Change the ownership of your `nextcloud` directory to your HTTP user, like this example for Debian/Ubuntu. You must run `occ` as your HTTP user; see [Run occ as your HTTP user](#):

```
$ sudo chown -R www-data:www-data /var/www/nextcloud/
```

3. Use the `occ` command to complete your installation. This takes the place of running the graphical Installation Wizard:

```
$ cd /var/www/nextcloud/
$ sudo -u www-data php occ maintenance:install --database \
```

(continues on next page)

(continued from previous page)

```
"mysql" --database-name "nextcloud" --database-user "root" --database-pass \  
"password" --admin-user "admin" --admin-pass "password"  
Nextcloud is not installed - only a limited number of commands are available  
Nextcloud was successfully installed
```

Note that you must change to the root Nextcloud directory, as in the example above, to run `occ maintenance:install`, or the installation will fail with a PHP fatal error message.

Supported databases are:

```
- sqlite (SQLite3 - Nextcloud Community edition only)  
- mysql (MySQL/MariaDB)  
- pgsql (PostgreSQL)  
- oci (Oracle 11g currently only possible if you contact us at https://nextcloud.com/  
  ↳ enterprise as part of a subscription)
```

See *Command line installation* for more information.

4.6 Supported apps

Below is the list of apps supported for Nextcloud latest. Supported here means that we'll accept bugreports and resolve them in these apps with regard to functionality and compatibility with Nextcloud latest. To get access to work-arounds, long term support, priority bug fixing and custom consulting, contact Nextcloud GmbH.

All apps are licensed under AGPLv3.

4.6.1 Nextcloud Files

- Accessibility
- Activity
- Auditing / Logging
- Antivirus for files
- Brute-force settings
- Circles
- Collaborative Tags
- Comments
- Contacts Interaction
- Data Request
- Default encryption module
- Deleted files
- External Sites
- External storage support
- Federated file sharing
- Federation

- File sharing
- Files access control
- Files
- Files Automated Tagging
- First run wizard
- Flow
- Full Text Search
- Full Text Search - Elasticsearch Platform
- Full Text Search - Files
- Full Text Search - Tesseract OCR
- Group folders
- Guests
- LDAP user and group backend
- Log Reader
- Monitoring
- Nextcloud announcements
- Notifications
- Password policy
- PDF Viewer
- Photos
- Provisioning API
- Recommendations
- Right click
- Share by mail
- SharePoint Backend
- SSO & SAML authentication
- **Social sharing via:**
 - Diaspora
 - Email
 - Facebook
 - Twitter
- Terms of Service
- Text
- Theming
- Two factor backup codes
- Two factor TOTP Provider

- Two factor U2F
- Update Notifications
- Versions
- Video Player
- WebDAV endpoint

4.6.2 Nextcloud Groupware

- Calendar
- Contacts
- Deck
- Mail

4.6.3 Nextcloud Talk

- Talk

4.6.4 Collaborative editing

- Collabora Online
- ONLYOFFICE

4.6.5 Global Scale

- Global Site Selector
- Lookup Server Connector

4.7 SELinux configuration

When you have SELinux enabled on your Linux distribution, you may run into permissions problems after a new Nextcloud installation, and see `permission denied` errors in your Nextcloud logs.

The following settings should work for most SELinux systems that use the default distro profiles. Run these commands as root, and remember to adjust the filepaths in these examples for your installation:

```
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/data(/.*)?'
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/config(/.*)?'
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/apps(/.*)?'
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/.htaccess'
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/.user.ini'
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/3rdparty/aws/aws-
↳ sdk-php/src/data/logs(/.*)?'

restorecon -Rv '/var/www/html/nextcloud/'
```

If you uninstall Nextcloud you need to remove the Nextcloud directory labels. To do this execute the following commands as root after uninstalling Nextcloud:

```
semanage fcontext -d '/var/www/html/nextcloud/data(/.*)?'
semanage fcontext -d '/var/www/html/nextcloud/config(/.*)?'
semanage fcontext -d '/var/www/html/nextcloud/apps(/.*)?'
semanage fcontext -d '/var/www/html/nextcloud/.htaccess'
semanage fcontext -d '/var/www/html/nextcloud/.user.ini'
semanage fcontext -d '/var/www/html/nextcloud/3rdparty/aws/aws-sdk-php/src/data/logs(/.
↪*)?'

restorecon -Rv '/var/www/html/nextcloud/'
```

If you have customized SELinux policies and these examples do not work, you must give the HTTP server write access to these directories:

```
/var/www/html/nextcloud/data
/var/www/html/nextcloud/config
/var/www/html/nextcloud/apps
```

4.7.1 Enable updates via the web interface

To enable updates via the web interface, you may need this to enable writing to the directories:

```
setsebool httpd_unified on
```

When the update is completed, disable write access:

```
setsebool -P httpd_unified off
```

4.7.2 Disallow write access to the whole web directory

For security reasons it's suggested to disable write access to all folders in /var/www/ (default):

```
setsebool -P httpd_unified off
```

4.7.3 Allow access to a remote database

An additional setting is needed if your installation is connecting to a remote database:

```
setsebool -P httpd_can_network_connect_db on
```

4.7.4 Allow access to LDAP server

Use this setting to allow LDAP connections:

```
setsebool -P httpd_can_connect_ldap on
```

4.7.5 Allow access to remote network

Nextcloud requires access to remote networks for functions such as Server-to-Server sharing, external storages or the app store. To allow this access use the following setting:

```
setsebool -P httpd_can_network_connect on
```

4.7.6 Allow access to network memcache

This setting is not required if `httpd_can_network_connect` is already on:

```
setsebool -P httpd_can_network_memcache on
```

4.7.7 Allow access to SMTP/sendmail

If you want to allow Nextcloud to send out e-mail notifications via sendmail you need to use the following setting:

```
setsebool -P httpd_can_sendmail on
```

4.7.8 Allow access to CIFS/SMB

If you have placed your datadir on a CIFS/SMB share use the following setting:

```
setsebool -P httpd_use_cifs on
```

4.7.9 Allow access to FuseFS

If your data folder resides on a Fuse Filesystem (e.g. EncFS etc), this setting is required as well:

```
setsebool -P httpd_use_fusefs on
```

4.7.10 Allow access to GPG for Rainloop

If you use a the rainloop webmail client app which supports GPG/PGP, you might need this:

```
setsebool -P httpd_use_gpg on
```

4.7.11 Troubleshooting

For general Troubleshooting of SELinux and its profiles try to install the package `setroubleshoot` and run:

```
sealert -a /var/log/audit/audit.log > /path/to/mylogfile.txt
```

to get a report which helps you configuring your SELinux profiles.

Another tool for troubleshooting is to enable a single ruleset for your Nextcloud directory:

```
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud(/.*)?'\nrestorecon -RF /var/www/html/nextcloud
```

It is much stronger security to have a more fine-grained ruleset as in the examples at the beginning, so use this only for testing and troubleshooting. It has a similar effect to disabling SELinux, so don't use it on production systems.

4.8 NGINX configuration

Warning: Please note that webserver other than Apache 2.x are not officially supported.

Note: This page covers example NGINX configurations to run a Nextcloud server. These configurations examples were originally provided by @josh4trunks and are exclusively community-maintained. (Thank you contributors!)

- You need to insert the following code into **your Nginx configuration file**.
- Adjust **server_name**, **root**, **ssl_certificate** and **ssl_certificate_key** to suit your needs.
- Make sure your SSL certificates are readable by the server (see [nginx HTTP SSL Module documentation](#)).
- Be careful about line breaks if you copy the examples, as long lines may be broken for page formatting.
- Some environments might need a `cgi.fix_pathinfo` set to 1 in their `php.ini`.

4.8.1 Nextcloud in the webroot of NGINX

The following configuration should be used when Nextcloud is placed in the webroot of your nginx installation. In this example it is `/var/www/nextcloud` and it is accessed via `http(s)://cloud.example.com/`

```
upstream php-handler {
    server 127.0.0.1:9000;
    #server unix:/var/run/php/php7.4-fpm.sock;
}

server {
    listen 80;
    listen [::]:80;
    server_name cloud.example.com;

    # Enforce HTTPS
    return 301 https://$server_name$request_uri;
```

(continues on next page)

(continued from previous page)

```

}

server {
    listen 443          ssl http2;
    listen [::]:443 ssl http2;
    server_name cloud.example.com;

    # Use Mozilla's guidelines for SSL/TLS settings
    # https://mozilla.github.io/server-side-tls/ssl-config-generator/
    ssl_certificate      /etc/ssl/nginx/cloud.example.com.crt;
    ssl_certificate_key  /etc/ssl/nginx/cloud.example.com.key;

    # HSTS settings
    # WARNING: Only add the preload option once you read about
    # the consequences in https://hstspreload.org/. This option
    # will add the domain to a hardcoded list that is shipped
    # in all major browsers and getting removed from this list
    # could take several months.
    #add_header Strict-Transport-Security "max-age=15768000; includeSubDomains; preload;
    ↪" always;

    # set max upload size
    client_max_body_size 512M;
    fastcgi_buffers 64 4K;

    # Enable gzip but do not remove ETag headers
    gzip on;
    gzip_vary on;
    gzip_comp_level 4;
    gzip_min_length 256;
    gzip_proxied expired no-cache no-store private no_last_modified no_etag auth;
    ↪gzip_types application/atom+xml application/javascript application/json application/
    ↪ld+json application/manifest+json application/rss+xml application/vnd.geo+json
    ↪application/vnd.ms-fontobject application/x-font-ttf application/x-web-app-
    ↪manifest+json application/xhtml+xml application/xml font/opentype image/bmp image/
    ↪svg+xml image/x-icon text/cache-manifest text/css text/plain text/vcard text/vnd.rim.
    ↪location.xloc text/vtt text/x-component text/x-cross-domain-policy;

    # Pagespeed is not supported by Nextcloud, so if your server is built
    # with the `ngx_pagespeed` module, uncomment this line to disable it.
    #pagespeed off;

    # HTTP response headers borrowed from Nextcloud `.htaccess`
    add_header Referrer-Policy          "no-referrer"    always;
    add_header X-Content-Type-Options   "nosniff"       always;
    add_header X-Download-Options       "noopen"         always;
    add_header X-Frame-Options          "SAMEORIGIN"     always;
    add_header X-Permitted-Cross-Domain-Policies "none"     always;
    add_header X-Robots-Tag             "none"           always;
    add_header X-XSS-Protection         "1; mode=block"  always;

    # Remove X-Powered-By, which is an information leak

```

(continues on next page)

(continued from previous page)

```

fastcgi_hide_header X-Powered-By;

# Path to the root of your installation
root /var/www/nextcloud;

# Specify how to handle directories -- specifying `/index.php$request_uri`
# here as the fallback means that Nginx always exhibits the desired behaviour
# when a client requests a path that corresponds to a directory that exists
# on the server. In particular, if that directory contains an index.php file,
# that file is correctly served; if it doesn't, then the request is passed to
# the front-end controller. This consistent behaviour means that we don't need
# to specify custom rules for certain paths (e.g. images and other assets,
# `/updater`, `/ocm-provider`, `/ocs-provider`), and thus
# `try_files $uri $uri/ /index.php$request_uri`
# always provides the desired behaviour.
index index.php index.html /index.php$request_uri;

# Rule borrowed from `.htaccess` to handle Microsoft DAV clients
location = / {
    if ( $http_user_agent ~ ^DavClnt ) {
        return 302 /remote.php/webdav/$is_args$args;
    }
}

location = /robots.txt {
    allow all;
    log_not_found off;
    access_log off;
}

# Make a regex exception for `/.well-known` so that clients can still
# access it despite the existence of the regex rule
# `location ~ /\.(|autotest|...)` which would otherwise handle requests
# for `/.well-known`.
location ^~ /.well-known {
    # The following 6 rules are borrowed from `.htaccess`

    location = /.well-known/carddav      { return 301 /remote.php/dav/; }
    location = /.well-known/caldav      { return 301 /remote.php/dav/; }
    # Anything else is dynamically handled by Nextcloud
    location ^~ /.well-known            { return 301 /index.php$uri; }

    try_files $uri $uri/ =404;
}

# Rules borrowed from `.htaccess` to hide certain paths from clients
location ~ ^/(?build|tests|config|lib|3rdparty|templates|data)(?=$|/) { return 404;
↪ }
location ~ ^/(?:\.|autotest|occ|issue|indie|db_|console) { return 404; }

# Ensure this block, which passes PHP files to the PHP process, is above the blocks
# which handle static assets (as seen below). If this block is not declared first,

```

(continues on next page)

(continued from previous page)

```

# then Nginx will encounter an infinite rewriting loop when it prepends `/index.php`
# to the URI, resulting in a HTTP 500 error response.
location ~ /\.php(?:$|/) {
    # Required for legacy support
    rewrite ^/(?!index|remote|public|cron|core/ajax/update|status|ocs|v[12]|updater|/.+|oc[ms]-provider|/.+|/.+|richdocumentscode/proxy) /index.php$request_
    uri;

    fastcgi_split_path_info ^(.+?\.php)(/.*)$;
    set $path_info $fastcgi_path_info;

    try_files $fastcgi_script_name =404;

    include fastcgi_params;
    fastcgi_param SCRIPT_FILENAME $document_root$fastcgi_script_name;
    fastcgi_param PATH_INFO $path_info;
    fastcgi_param HTTPS on;

    fastcgi_param modHeadersAvailable true;           # Avoid sending the security_
    headers twice
    fastcgi_param front_controller_active true;       # Enable pretty urls
    fastcgi_pass php-handler;

    fastcgi_intercept_errors on;
    fastcgi_request_buffering off;
}

location ~ \.(?:css|js|svg|gif|map)$ {
    try_files $uri /index.php$request_uri;
    expires 6M;           # Cache-Control policy borrowed from `.htaccess`
    access_log off;       # Optional: Don't log access to assets
}

location ~ \.woff2?$ {
    try_files $uri /index.php$request_uri;
    expires 7d;           # Cache-Control policy borrowed from `.htaccess`
    access_log off;       # Optional: Don't log access to assets
}

location / {
    try_files $uri $uri/ /index.php$request_uri;
}
}

```

4.8.2 Nextcloud in a subdir of the NGINX webroot

The following config should be used when Nextcloud is placed within a subdir of the webroot of your nginx installation. In this example the Nextcloud files are located at `/var/www/nextcloud` and the Nextcloud instance is accessed via `http(s)://cloud.example.com/nextcloud/`. The configuration differs from the “Nextcloud in webroot” configuration above in the following ways:

- All requests for `/nextcloud` are encapsulated within a single location block, namely `location ^~ /nextcloud`.
- The string `/nextcloud` is prepended to all prefix paths.
- The root of the domain is mapped to `/var/www` rather than `/var/www/nextcloud`, so that the URI `/nextcloud` is mapped to the server directory `/var/www/nextcloud`.
- The blocks that handle requests for paths outside of `/nextcloud` (i.e. `/robots.txt` and `/.well-known`) are pulled out of the `location ^~ /nextcloud` block.
- The block which handles `/.well-known` doesn't need a regex exception, since the rule which prevents users from accessing hidden folders at the root of the Nextcloud installation no longer matches that path.

```

upstream php-handler {
    server 127.0.0.1:9000;
    #server unix:/var/run/php/php7.4-fpm.sock;
}

server {
    listen 80;
    listen [::]:80;
    server_name cloud.example.com;

    # Enforce HTTPS just for `/nextcloud`
    location /nextcloud {
        return 301 https://$server_name$request_uri;
    }
}

server {
    listen 443      ssl http2;
    listen [::]:443 ssl http2;
    server_name cloud.example.com;

    # Use Mozilla's guidelines for SSL/TLS settings
    # https://mozilla.github.io/server-side-tls/ssl-config-generator/
    ssl_certificate      /etc/ssl/nginx/cloud.example.com.crt;
    ssl_certificate_key  /etc/ssl/nginx/cloud.example.com.key;

    # HSTS settings
    # WARNING: Only add the preload option once you read about
    # the consequences in https://hstspreload.org/. This option
    # will add the domain to a hardcoded list that is shipped
    # in all major browsers and getting removed from this list
    # could take several months.
    #add_header Strict-Transport-Security "max-age=15768000; includeSubDomains; preload;
    ↪" always;

```

(continues on next page)

(continued from previous page)

```

# Path to the root of the domain
root /var/www;

location = /robots.txt {
    allow all;
    log_not_found off;
    access_log off;
}

location /.well-known {
    # The following 6 rules are borrowed from `.htaccess`

    location = /.well-known/carddav { return 301 /nextcloud/remote.php/dav; }
    location = /.well-known/caldav { return 301 /nextcloud/remote.php/dav; }

    # Anything else is dynamically handled by Nextcloud
    location ^~ /.well-known { return 301 /nextcloud/index.php$uri; }

    try_files $uri $uri/ =404;
}

location ^~ /nextcloud {
    # set max upload size
    client_max_body_size 512M;
    fastcgi_buffers 64 4K;

    # Enable gzip but do not remove ETag headers
    gzip on;
    gzip_vary on;
    gzip_comp_level 4;
    gzip_min_length 256;
    gzip_proxied expired no-cache no-store private no_last_modified no_etag auth;
    gzip_types application/atom+xml application/javascript application/json
    ↪ application/ld+json application/manifest+json application/rss+xml application/vnd.
    ↪ geo+json application/vnd.ms-fontobject application/x-font-ttf application/x-web-app-
    ↪ manifest+json application/xhtml+xml application/xml font/opentype image/bmp image/
    ↪ svg+xml image/x-icon text/cache-manifest text/css text/plain text/vcard text/vnd.rim.
    ↪ location.xloc text/vtt text/x-component text/x-cross-domain-policy;

    # Pagespeed is not supported by Nextcloud, so if your server is built
    # with the `ngx_pagespeed` module, uncomment this line to disable it.
    #pagespeed off;

    # HTTP response headers borrowed from Nextcloud `.htaccess`
    add_header Referrer-Policy "no-referrer" always;
    add_header X-Content-Type-Options "nosniff" always;
    add_header X-Download-Options "noopen" always;
    add_header X-Frame-Options "SAMEORIGIN" always;
    add_header X-Permitted-Cross-Domain-Policies "none" always;
    add_header X-Robots-Tag "none" always;
    add_header X-XSS-Protection "1; mode=block" always;

```

(continues on next page)

(continued from previous page)

```

# Remove X-Powered-By, which is an information leak
fastcgi_hide_header X-Powered-By;

# Specify how to handle directories -- specifying `/nextcloud/index.php$request_
uri`
# here as the fallback means that Nginx always exhibits the desired behaviour
# when a client requests a path that corresponds to a directory that exists
# on the server. In particular, if that directory contains an index.php file,
# that file is correctly served; if it doesn't, then the request is passed to
# the front-end controller. This consistent behaviour means that we don't need
# to specify custom rules for certain paths (e.g. images and other assets,
# `/updater`, `/ocm-provider`, `/ocs-provider`), and thus
# `try_files $uri $uri/ /nextcloud/index.php$request_uri`
# always provides the desired behaviour.
index index.php index.html /nextcloud/index.php$request_uri;

# Rule borrowed from `.htaccess` to handle Microsoft DAV clients
location = /nextcloud {
    if ( $http_user_agent ~ ^DavClnt ) {
        return 302 /nextcloud/remote.php/webdav/$is_args$args;
    }
}

# Rules borrowed from `.htaccess` to hide certain paths from clients
location ~ ^/nextcloud/(?!build|tests|config|lib|3rdparty|templates|data)(?:$|/)_
{ return 404; }
location ~ ^/nextcloud/(?!\.|autotest|occ|issue|indie|db_|console)
{ return 404; }

# Ensure this block, which passes PHP files to the PHP process, is above the
blocks
# which handle static assets (as seen below). If this block is not declared
first,
# then Nginx will encounter an infinite rewriting loop when it prepends
# `/nextcloud/index.php` to the URI, resulting in a HTTP 500 error response.
location ~ \.php(?:$|/) {
    # Required for legacy support
    rewrite ^/nextcloud/(?!index|remote|public|cron|core/ajax\|
update|status|ocs/v[12]|updater\|.+|oc[ms]-provider\|.+|.\richdocumentscode\|proxy)_
/nextcloud/index.php$request_uri;

    fastcgi_split_path_info ^(.+?\.php)(/.*)$;
    set $path_info $fastcgi_path_info;

    try_files $fastcgi_script_name =404;

    include fastcgi_params;
    fastcgi_param SCRIPT_FILENAME $document_root$fastcgi_script_name;
    fastcgi_param PATH_INFO $path_info;
    fastcgi_param HTTPS on;

    fastcgi_param modHeadersAvailable true;           # Avoid sending the security_
headers twice

```

(continues on next page)

(continued from previous page)

```

    fastcgi_param front_controller_active true;    # Enable pretty urls
    fastcgi_pass php-handler;

    fastcgi_intercept_errors on;
    fastcgi_request_buffering off;
}

location ~ \.(?:css|js|svg|gif|map)$ {
    try_files $uri /nextcloud/index.php$request_uri;
    expires 6M;          # Cache-Control policy borrowed from `.htaccess`
    access_log off;      # Optional: Don't log access to assets
}

location ~ \.woff2?$ {
    try_files $uri /nextcloud/index.php$request_uri;
    expires 7d;          # Cache-Control policy borrowed from `.htaccess`
    access_log off;      # Optional: Don't log access to assets
}

location /nextcloud {
    try_files $uri $uri/ /nextcloud/index.php$request_uri;
}
}

```

4.8.3 Tips and tricks

Suppressing log messages

If you're seeing meaningless messages in your logfile, for example client denied by server configuration: /var/www/data/htaccessstest.txt, add this section to your nginx configuration to suppress them:

```

location = /data/htaccessstest.txt {
    allow all;
    log_not_found off;
    access_log off;
}

```

JavaScript (.js) or CSS (.css) files not served properly

A common issue with custom nginx configs is that JavaScript (.js) or CSS (.css) files are not served properly leading to a 404 (File not found) error on those files and a broken webinterface.

This could be caused by the:

```
location ~* \.(?:css|js)$ {
```

block shown above not located **below** the:

```
location ~ \.php(?:$|\/) {
```

block. Other custom configurations like caching JavaScript (.js) or CSS (.css) files via gzip could also cause such issues. Another cause of this issue could be not properly including mimetypes in the http block, as shown [here](#).

Upload of files greater than 10 MiB fails

If you configure nginx (globally) to block all requests to (hidden) dot files, it may be not possible to upload files greater than 10 MiB using the webpage due to Nextclouds requirement to upload the file to an url ending with /.file.

You may require to change:

```
location ~ /\. {
```

to the following to re-allow file uploads:

```
location ~ /\.(!file).* {
```

See *issue #8802 on nextcloud/server* <<https://github.com/nextcloud/server/issues/8802>> for more information.

Login loop without any clue in access.log, error.log, nor nextcloud.log

If you after fresh installation (Centos 7 with nginx) have problem with first login, you should as first check these files:

```
tail /var/www/nextcloud/data/nextcloud.log
tail /var/log/nginx/access.log
tail /var/log/nginx/error.log
```

If you just see some correct requests in access log, but no login happens, you check access rights for php session and wsdncache directory. Try to check permissions and execute change if needed:

```
chown nginx:nginx /var/lib/php/session/
chown root:nginx /var/lib/php/wsdncache/
chown root:nginx /var/lib/php/opcache/
```

4.9 Hardening and security guidance

Nextcloud aims to ship with secure defaults that do not need to get modified by administrators. However, in some cases some additional security hardening can be applied in scenarios where the administrator has complete control over the Nextcloud instance. This page assumes that you run Nextcloud Server on Apache2 in a Linux environment.

Note: Nextcloud will warn you in the administration interface if some critical security-relevant options are missing. However, it is still up to the server administrator to review and maintain system security.

4.9.1 Passwords

Storage of access tokens

Upon successful authentication, Nextcloud issues an access token that clients will use for all future HTTP requests. This access token uniquely identifies a user and should not be stored on any system other than the client requesting it. The user password is also stored encrypted in the Nextcloud database. For encryption of the password, the token and an instance-specific secret is used.

Leakage of the access token can have negative security consequences. Depending on the data access by the actor, the risk here is different:

- An actor with access to only the access token can impersonate users and login as them.
- An actor with access to the access token, the Nextcloud config file, and the Nextcloud database can decrypt user passwords stored in the database.

Limit on password length

Nextcloud uses the bcrypt algorithm, and thus for security and performance reasons, e.g. Denial of Service as CPU demand increases exponentially, it only verifies the first 72 characters of passwords. This applies to all passwords that you use in Nextcloud: user passwords, passwords on link shares, and passwords on external shares.

4.9.2 Operating system

Give PHP read access to `/dev/urandom`

Nextcloud uses a [RFC 4086](#) (“Randomness Requirements for Security”) compliant mixer to generate cryptographically secure pseudo-random numbers. This means that when generating a random number Nextcloud will request multiple random numbers from different sources and derive from these the final random number.

The random number generation also tries to request random numbers from `/dev/urandom`, thus it is highly recommended to configure your setup in such a way that PHP is able to read random data from it.

Note: When having an `open_basedir` configured within your `php.ini` file, make sure to include `/dev/urandom`.

Enable hardening modules such as SELinux

It is highly recommended to enable hardening modules such as SELinux where possible. See [SELinux configuration](#) to learn more about SELinux.

4.9.3 Deployment

Place data directory outside of the web root

It is highly recommended to place your data directory outside of the Web root (i.e. outside of `/var/www`). It is easiest to do this on a new installation.

Disable preview image generation

Nextcloud is able to generate preview images of common filetypes such as images or text files. By default the preview generation for some file types that we consider secure enough for deployment is enabled by default. However, administrators should be aware that these previews are generated using PHP libraries written in C which might be vulnerable to attack vectors.

For high security deployments we recommend disabling the preview generation by setting the `enable_previews` switch to `false` in `config.php`. As an administrator you are also able to manage which preview providers are enabled by modifying the `enabledPreviewProviders` option switch.

4.9.4 Use HTTPS

Using Nextcloud without using an encrypted HTTPS connection opens up your server to a man-in-the-middle (MITM) attack, and risks the interception of user data and passwords. It is a best practice, and highly recommended, to always use HTTPS on production servers, and to never allow unencrypted HTTP.

How to setup HTTPS on your Web server depends on your setup; please consult the documentation for your HTTP server. The following examples are for Apache.

Redirect all unencrypted traffic to HTTPS

To redirect all HTTP traffic to HTTPS administrators are encouraged to issue a permanent redirect using the 301 status code. When using Apache this can be achieved by a setting such as the following in the Apache VirtualHosts configuration:

```
<VirtualHost *:80>
    ServerName cloud.nextcloud.com
    Redirect permanent / https://cloud.nextcloud.com/
</VirtualHost>
```

Enable HTTP Strict Transport Security

While redirecting all traffic to HTTPS is good, it may not completely prevent man-in-the-middle attacks. Thus administrators are encouraged to set the HTTP Strict Transport Security header, which instructs browsers to not allow any connection to the Nextcloud instance using HTTP, and it attempts to prevent site visitors from bypassing invalid certificate warnings.

This can be achieved by setting the following settings within the Apache VirtualHost file:

```
<VirtualHost *:443>
    ServerName cloud.nextcloud.com
    <IfModule mod_headers.c>
        Header always set Strict-Transport-Security "max-age=15552000; includeSubDomains"
    </IfModule>
</VirtualHost>
```

Warning: We recommend the additional setting `; preload` to be added to that header. Then the domain will be added to a hardcoded list that is shipped with all major browsers and enforce HTTPS upon those domains. See the [HSTS preload website for more information](#). Due to the policy of this list you need to add it to the above example

for yourself once you are sure that this is what you want. [Removing the domain from this list](#) could take some months until it reaches all installed browsers.

This example configuration will make all subdomains only accessible via HTTPS. If you have subdomains not accessible via HTTPS, remove `includeSubDomains`.

This requires the `mod_headers` extension in Apache.

Proper SSL configuration

Default SSL configurations by Web servers are often not state-of-the-art, and require fine-tuning for an optimal performance and security experience. The available SSL ciphers and options depend completely on your environment and thus giving a generic recommendation is not really possible.

We recommend using the [Mozilla SSL Configuration Generator](#) to generate a suitable configuration suited for your environment. To verify your configuration you can use the free [Web TLS Profiler](#) service. This service gives detailed error messages, if your server's TLS settings deviate from the Mozilla Configuration. Another useful tool to check your server's TLS configuration is the free [Qualys SSL Labs Test](#) which provides general information about the TLS settings.

Also ensure that HTTP compression is disabled to mitigate the BREACH attack.

4.9.5 Use a dedicated domain for Nextcloud

Administrators are encouraged to install Nextcloud on a dedicated domain such as `cloud.domain.tld` instead of `domain.tld` to gain all the benefits offered by the Same-Origin-Policy.

4.9.6 Ensure that your Nextcloud instance is installed in a DMZ

As Nextcloud supports features such as Federated File Sharing we do not consider Server Side Request Forgery (SSRF) part of our threat model. In fact, given all our external storage adapters this can be considered a feature and not a vulnerability.

This means that a user on your Nextcloud instance could probe whether other hosts are accessible from the Nextcloud network. If you do not want this you need to ensure that your Nextcloud is properly installed in a segregated network and proper firewall rules are in place.

4.9.7 Serve security related headers by the Web server

Basic security headers are served by Nextcloud already in a default environment. These include:

- **X-Content-Type-Options: nosniff**
 - Instructs some browsers to not sniff the mimetype of files. This is used for example to prevent browsers from interpreting text files as JavaScript.
- **X-XSS-Protection: 1; mode=block**
 - Instructs browsers to enable their browser side Cross-Site-Scripting filter.
- **X-Robots-Tag: none**
 - Instructs search machines to not index these pages.
- **X-Frame-Options: SAMEORIGIN**

- Prevents embedding of the Nextcloud instance within an iframe from other domains to prevent Click-jacking and other similar attacks.
- **Referrer-Policy: no-referrer**
 - The default *no-referrer* policy instructs the browser not to send referrer information along with requests to any origin.

These headers are hard-coded into the Nextcloud server, and need no intervention by the server administrator.

For optimal security, administrators are encouraged to serve these basic HTTP headers by the Web server to enforce them on response. To do this Apache has to be configured to use the `.htaccess` file and the following Apache modules need to be enabled:

- `mod_headers`
- `mod_env`

Administrators can verify whether this security change is active by accessing a static resource served by the Web server and verify that the above mentioned security headers are shipped.

4.9.8 Connections to remote servers

Some Nextcloud functionality requires connecting to remote servers. Depending on your server setup those are possible connections:

- `www.nextcloud.com`, `www.startpage.com`, `www.eff.org`, `www.edri.org` for checking the internet connection
- `apps.nextcloud.com` for the available apps
- `updates.nextcloud.com` for Nextcloud updates
- `lookup.nextcloud.com` For updating and lookup in the federated sharing addressbook
- `push-notifications.nextcloud.com` for sending push notifications to mobile clients
- `surveyserver.nextcloud.com` if the admin has agreed to share anonymized data
- Any remote Nextcloud server that is connected with federated sharing

4.9.9 Setup fail2ban

Exposing your server to the internet will inevitably lead to the exposure of the services running on the internet-exposed ports to brute force login attempts.

Fail2ban is a service that uses iptables to automatically drop connections for a pre-defined amount of time from IPs that continuously failed to authenticate to the configured services.

In order to setup fail2ban, you first need to download and install it on your server. Downloads for several distributions can be found on [fail2ban download page](#). It is often available from most distributions' package managers (e.g. `apt-get`).

The standard path for fail2ban's configuration is `/etc/fail2ban`.

Setup a filter and a jail for Nextcloud

A filter defines regex rules to identify when users fail to authenticate on Nextcloud's user interface, WebDAV, or use an untrusted domain to access the server.

Create a file in `/etc/fail2ban/filter.d` named `nextcloud.conf` with the following contents:

```
[Definition]
_groupsre = (?:{(?:,?\s*"w+":(?:[""]+\s+|\w+))*})
failregex = ^\{%( _groupsre)s,?\s*"remoteAddr": "<HOST>"%( _groupsre)s,?\s*"message": "Login_
↪failed:
           ^\{%( _groupsre)s,?\s*"remoteAddr": "<HOST>"%( _groupsre)s,?\s*"message":
↪"Trusted domain error.
datepattern = ,?\s*"time"\s*:\s*"%%Y-%%m-%%d[T ]%%H:%%M:%%S(%%z)?"
```

The jail file defines how to handle the failed authentication attempts found by the Nextcloud filter.

Create a file in `/etc/fail2ban/jail.d` named `nextcloud.local` with the following contents:

```
[nextcloud]
backend = auto
enabled = true
port = 80,443
protocol = tcp
filter = nextcloud
maxretry = 3
bantime = 86400
findtime = 43200
logpath = /path/to/data/directory/nextcloud.log
```

Ensure to replace `logpath` with your installation's `nextcloud.log` location. If you are using ports other than 80 and 443 for your Web server you should replace those too. The `bantime` and `findtime` are defined in seconds.

Restart the fail2ban service. You can check the status of your Nextcloud jail by running:

```
fail2ban-client status nextcloud
```

4.10 Server tuning

4.10.1 Using cron to perform background jobs

See *Background jobs* for a description and the benefits.

4.10.2 Reducing system load

High system load will slow down Nextcloud and might also lead to other unwanted side effects. To reduce load you should first identify the source of the problem. Tools such as `htop`, `iotop`, `netdata` or `glances` will help to identify the process or the drive that slows down your system. First you should make sure that you installed/assigned enough RAM. Swap usage should be prevented by all means. If you run your database inside a VM, you should not store it inside a VM image file. Better put it on a dedicated block device to reduce latency due to multiple abstraction layers.

4.10.3 Caching

Caching improves performance by storing data, code, and other objects in memory. Memory cache configuration for the Nextcloud server must be installed and configured. See [Memory caching](#).

4.10.4 Using MariaDB/MySQL instead of SQLite

MySQL or MariaDB are preferred because of the [performance limitations](#) of SQLite with highly concurrent applications, like Nextcloud.

See the section [Database configuration](#) for how to configure Nextcloud for MySQL or MariaDB. If your installation is already running on SQLite then it is possible to convert to MySQL or MariaDB using the steps provided in [Converting database type](#).

In smaller installations you might not want to set up a separate cache. However you can still tune your database. The following example is suited for a database smaller than 1GB. MySQL will consume up to 1GB of RAM for caching. Please make sure that your system has sufficient free RAM after the change, so that it does not start to use your swap partition, when it receives a burst of requests. In the given example your `/etc/mysql/conf.d/mysql.cnf` might contain the following lines. (beware that this is the block for mysqld not mysql)

```
[mysqld]
innodb_buffer_pool_size=1G
innodb_io_capacity=4000
```

4.10.5 Using Redis-based transactional file locking

File locking is enabled by default, using the database locking backend. This places a significant load on your database. See the section [Transactional file locking](#) for how to configure Nextcloud to use Redis-based Transactional File Locking.

4.10.6 SSL / encryption app

SSL (HTTPS) and file encryption/decryption can be offloaded to a processor's AES-NI extension. This can both speed up these operations while lowering processing overhead. This requires a processor with the [AES-NI instruction set](#).

Here are some examples how to check if your CPU / environment supports the AES-NI extension:

- For each CPU core present: `grep flags /proc/cpuinfo` or as a summary for all cores: `grep -m 1 '^flags' /proc/cpuinfo` If the result contains any `aes`, the extension is present.
- Search eg. on the Intel web if the processor used supports the extension [Intel Processor Feature Filter](#) You may set a filter by "AES New Instructions" to get a reduced result set.
- For versions of openssl `>= 1.0.1`, AES-NI does not work via an engine and will not show up in the `openssl engine` command. It is active by default on the supported hardware. You can check the openssl version via `openssl version -a`
- If your processor supports AES-NI but it does not show up eg via `grep` or `coreinfo`, it is maybe disabled in the BIOS.
- If your environment runs virtualized, check the virtualization vendor for support.

4.10.7 Enable HTTP2 for faster loading

HTTP2 has [huge speed improvements](#) over HTTP with multiple request. Most browsers already support HTTP2 over SSL (HTTPS). So refer to your server manual for guides on how to use HTTP2.

You can check if your application already uses HTTP2 or not by running the simple curl command

```
..code:: sh curl -I https://mywebsite.com/
```

4.10.8 Tune PHP-FPM

If you are using a default installation of php-fpm you might have noticed excessive load times on the web interface or even sync issues. This is due to the fact that each simultaneous request of an element is handled by a separate PHP-FPM process. So even on a small installation you should allow more processes to run. For example on a machine with 4GB of RAM and 1GB of MySQL cache following values in your `www.conf` file should work:

```
pm = dynamic
pm.max_children = 120
pm.start_servers = 12
pm.min_spare_servers = 6
pm.max_spare_servers = 18
```

Depending on your current PHP version you should find this file e.g. under `/etc/php/7.4/fpm/pool.d/www.conf`

4.10.9 Enable PHP OPcache

The [OPcache](#) improves the performance of PHP applications by caching precompiled bytecode. We recommend at least the following settings:

```
opcache.enable=1
opcache.interned_strings_buffer=8
opcache.max_accelerated_files=10000
opcache.memory_consumption=128
opcache.save_comments=1
opcache.revalidate_freq=1
```

For more details check out the [official documentation](#) or [this blog post](#) about some recommended settings.

4.11 Example installation on Ubuntu 20.04 LTS

You can use `.deb` packages to install the required and recommended modules for a typical Nextcloud installation, using Apache and MariaDB, by issuing the following commands in a terminal:

```
sudo apt update
sudo apt install apache2 mariadb-server libapache2-mod-php7.4
sudo apt install php7.4-gd php7.4-mysql php7.4-curl php7.4-mbstring php7.4-intl
sudo apt install php7.4-gmp php7.4-bcmath php-imagick php7.4-xml php7.4-zip
```

- This installs the packages for the Nextcloud core system. If you are planning on running additional apps, keep in mind that they might require additional packages. See [Prerequisites for manual installation](#) for details.

Now you need to create a database user and the database itself by using the MySQL command line interface. The database tables will be created by Nextcloud when you login for the first time.

To start the MySQL command line mode use the following command and press the enter key when prompted for a password:

```
sudo /etc/init.d/mysql start
sudo mysql -uroot -p
```

Then a **MariaDB [root]>** prompt will appear. Now enter the following lines, replacing username and password with appropriate values, and confirm them with the enter key:

```
CREATE USER 'username'@'localhost' IDENTIFIED BY 'password';
CREATE DATABASE IF NOT EXISTS nextcloud CHARACTER SET utf8mb4 COLLATE utf8mb4_general_ci;
GRANT ALL PRIVILEGES ON nextcloud.* TO 'username'@'localhost';
FLUSH PRIVILEGES;
```

You can quit the prompt by entering:

```
quit;
```

Now download the archive of the latest Nextcloud version:

- Go to the [Nextcloud Download Page](#).
- Go to **Download Nextcloud Server > Download > Archive file for server owners** and download either the tar.bz2 or .zip archive.
- This downloads a file named nextcloud-x.y.z.tar.bz2 or nextcloud-x.y.z.zip (where x.y.z is the version number).
- Download its corresponding checksum file, e.g. nextcloud-x.y.z.tar.bz2.md5, or nextcloud-x.y.z.tar.bz2.sha256.
- Verify the MD5 or SHA256 sum:

```
md5sum -c nextcloud-x.y.z.tar.bz2.md5 < nextcloud-x.y.z.tar.bz2
sha256sum -c nextcloud-x.y.z.tar.bz2.sha256 < nextcloud-x.y.z.tar.bz2
md5sum -c nextcloud-x.y.z.zip.md5 < nextcloud-x.y.z.zip
sha256sum -c nextcloud-x.y.z.zip.sha256 < nextcloud-x.y.z.zip
```

- You may also verify the PGP signature:

```
wget https://download.nextcloud.com/server/releases/nextcloud-x.y.z.tar.bz2.asc
wget https://nextcloud.com/nextcloud.asc
gpg --import nextcloud.asc
gpg --verify nextcloud-x.y.z.tar.bz2.asc nextcloud-x.y.z.tar.bz2
```

- Now you can extract the archive contents. Run the appropriate unpacking command for your archive type:

```
tar -xjvf nextcloud-x.y.z.tar.bz2
unzip nextcloud-x.y.z.zip
```

- This unpacks to a single nextcloud directory. Copy the Nextcloud directory to its final destination. When you are running the Apache HTTP server you may safely install Nextcloud in your Apache document root:

```
cp -r nextcloud /path/to/webserver/document-root
```

where /path/to/webserver/document-root is replaced by the document root of your Web server:

```
cp -r nextcloud /var/www
```

On other HTTP servers it is recommended to install Nextcloud outside of the document root.

4.11.1 Next steps

After installing the prerequisites and extracting the nextcloud directory, you should follow the instructions for Apache configuration at [Apache Web server configuration](#). Once Apache is installed, you can optionally follow the [Installation on Linux](#) guide from [Pretty URLs](#) until [Other Web servers](#)

4.12 Example installation on CentOS 8

In this install tutorial we will be deploying CentOS 8, PHP 7.4, MariaDB, Redis as memcache and Nextcloud running on Apache.

Start off by installing a CentOS 8 minimal install. This should provide a sufficient platform to run a successful Nextcloud instance.

First install some dependencies you will be needing during installation, but which will also be useful in every day use situations:

```
dnf install -y epel-release yum-utils unzip curl wget \
bash-completion policycoreutils-python-utils mlocate bzip2
```

Now make sure your system is up to date:

```
dnf update -y
```

4.12.1 Apache

```
dnf install -y httpd
```

Create a virtualhost in `/etc/httpd/conf.d/nextcloud.conf` and add the following content to it:

```
<VirtualHost *:80>
    DocumentRoot /var/www/html/nextcloud/
    ServerName  your.server.com

    <Directory /var/www/html/nextcloud/>
        Require all granted
        AllowOverride All
        Options FollowSymLinks MultiViews

        <IfModule mod_dav.c>
            Dav off
        </IfModule>

    </Directory>
</VirtualHost>
```

See *Apache Web server configuration* for further details.

Make sure the apache web service is enabled and started:

```
systemctl enable httpd.service
systemctl start httpd.service
```

4.12.2 PHP

Note: CentOS 8 doesn't come with packages for the redis and imagick php extensions. Those can either be installed using pecl. Apart from the official PHP packages there are 3rdparty repositories available at <https://rpms.remirepo.net>. Using remirepo you can also install the latest PHP version instead of the standard shipped one.

Setting up remirepo with PHP 7.4

More details can be found on <https://blog.remirepo.net/pages/Config-en>

Command to install the Remi repository configuration package:

```
dnf install https://rpms.remirepo.net/enterprise/remi-release-8.rpm
```

Command to install the yum-utils package (for the yum-config-manager command):

```
dnf install yum-utils
```

You want a single version which means replacing base packages from the distribution. Packages have the same name than the base repository, ie php-*. Some common dependencies are available in remi-safe repository, which is enabled by default.

You have to enable the module stream for 7.4:

```
dnf module reset php
dnf module install php:remi-7.4
dnf update
```

Installing PHP and the required modules

Next install the PHP modules needed for this install. Remember, because this is a limited basic install, we only install the necessary modules, not all of them. If you are making a more complete install, please refer to PHP module list in the source installation documentation, *Installation on Linux*.

```
dnf install -y php php-gd php-mbstring php-intl php-pecl-apcu\
php-mysqlnd php-opcache php-json php-zip
```

Installing optional modules redis/imagick

```
dnf install -y php-redis php-imagick
```

4.12.3 Database

As mentioned, we will be using MySQL/MariaDB as our database.:

```
dnf install -y mariadb mariadb-server
```

Make sure the database service is enabled to start at boot time.:

```
systemctl enable mariadb.service  
systemctl start mariadb.service
```

Improve MariaDB security.:

```
mysql_secure_installation
```

After you have done this, make sure you create a database with a username and password so that Nextcloud will have access to it. For further details on database setup and configuration, see the [Database configuration](#) documentation.

4.12.4 Redis

```
dnf install -y redis  
systemctl enable redis.service  
systemctl start redis.service
```

Installing Nextcloud

Nearly there, so keep at it, you are doing great!

Now download the archive of the latest Nextcloud version:

- Go to the [Nextcloud Download Page](#).
- Go to **Download Nextcloud Server > Download > Archive file for server owners** and download either the tar.bz2 or .zip archive.
- This downloads a file named nextcloud-x.y.z.tar.bz2 or nextcloud-x.y.z.zip (where x.y.z is the version number).
- Download its corresponding checksum file, e.g. nextcloud-x.y.z.tar.bz2.md5, or nextcloud-x.y.z.tar.bz2.sha256.
- Verify the MD5 or SHA256 sum:

```
md5sum -c nextcloud-x.y.z.tar.bz2.md5 < nextcloud-x.y.z.tar.bz2  
sha256sum -c nextcloud-x.y.z.tar.bz2.sha256 < nextcloud-x.y.z.tar.bz2  
md5sum -c nextcloud-x.y.z.zip.md5 < nextcloud-x.y.z.zip  
sha256sum -c nextcloud-x.y.z.zip.sha256 < nextcloud-x.y.z.zip
```

- You may also verify the PGP signature:

```
wget https://download.nextcloud.com/server/releases/nextcloud-x.y.z.tar.bz2.asc  
wget https://nextcloud.com/nextcloud.asc
```

(continues on next page)

(continued from previous page)

```
gpg --import nextcloud.asc
gpg --verify nextcloud-x.y.z.tar.bz2.asc nextcloud-x.y.z.tar.bz2
```

For the sake of the walk-through, we grabbed the latest version of Nextcloud in the form a zip file, confirmed the download with the above-mentioned command, and now we will extract it:

```
unzip nextcloud-*.zip
```

Copy the content over to the root directory of your webserver. In our case, we are using apache so it will be `/var/www/html/`:

```
cp -R nextcloud/ /var/www/html/
```

During the install process, no data folder is created, so we will create one manually to help with the installation wizard:

```
mkdir /var/www/html/nextcloud/data
```

Make sure that apache has read and write access to the whole nextcloud folder:

```
chown -R apache:apache /var/www/html/nextcloud
```

Restart apache:

```
systemctl restart httpd.service
```

Create a firewall rule for access to apache:

```
firewall-cmd --zone=public --add-service=http --permanent
firewall-cmd --reload
```

SELinux

Again, there is an extensive write-up done on SELinux which can be found at [SELinux configuration](#), so if you are using SELinux in Enforcing mode, please run the commands suggested on that page. The following commands only refers to this tutorial:

```
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/data(/.*)?'
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/config(/.*)?'
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/apps(/.*)?'
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/.htaccess'
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/.user.ini'
semanage fcontext -a -t httpd_sys_rw_content_t '/var/www/html/nextcloud/3rdparty/aws/aws-
↳ sdk-php/src/data/logs(/.*)?'

restorecon -R '/var/www/html/nextcloud/'

setsebool -P httpd_can_network_connect on
```

If you need more SELinux configs, refer to the above-mentioned URL, return to this tutorial.

Once done with SELinux, please head over to <http://your.server.com/nextcloud> and follow the steps as found [Installation wizard](#), where it will explain to you exactly how to proceed with the final part of the install, which is done as admin user through your web browser.

Note: If you use this tutorial, and you see warnings in the web browser after installation about OPcache not being enabled or configured correctly, you need to make the suggested changes in `/etc/opt/rh/rh-php74/php.d/10-opcache.ini` for the errors to disappear. These warnings will be on the Admin page, under Basic settings.

Because we used Redis as a memcache, you will need a config similar to the following example in `/var/www/html/nextcloud/config/config.php` which is auto-generated when you run the online installation wizard mentioned earlier.

Example config:

```
'memcache.distributed' => '\OC\Memcache\Redis',
'memcache.locking' => '\OC\Memcache\Redis',
'memcache.local' => '\OC\Memcache\APCu',
'redis' => array(
    'host' => 'localhost',
    'port' => 6379,
),
```

Remember, this tutorial is only for a basic setup of Nextcloud on CentOS 8, with PHP 7.4. If you are going to use more features like LDAP or Single Sign On, you will need additional PHP modules as well as extra configurations. So please visit the rest of the Admin manual, [Introduction](#), for detailed descriptions on how to get this done.

NEXTCLOUD CONFIGURATION

5.1 Warnings on admin page

Your Nextcloud server has a built-in configuration checker, and it reports its findings at the top of your Admin page. These are some of the warnings you might see, and what to do about them.

Security & setup warnings

- No memory cache has been configured. To enhance your performance please configure a memcache if available. Further information can be found in our [documentation](#).
- You are accessing this site via HTTP. We strongly suggest you configure your server to require using HTTPS instead.

Please double check the [installation guides](#) ↗, and check for any errors or warnings in the [log](#).

You can use the [Nextcloud Security Scan](#) to see if your system is up to date and well secured. We have ran this scan over public IP addresses in the past to try and reach out to [extremely outdated systems](#) and might again in the future. Please, protect your privacy and keep your server up to date! Privacy means little without security.

5.1.1 Cache warnings

“No memory cache has been configured. To enhance your performance please configure a memcache if available.” Nextcloud supports multiple php caching extensions:

- APCu (minimum required PHP extension version 4.0.6)
- Memcached
- Redis (minimum required PHP extension version: 2.2.6)

You will see this warning if you have no caches installed and enabled, or if your cache does not have the required minimum version installed; older versions are disabled because of performance problems.

If you see “{Cache} below version {Version} is installed. for stability and performance reasons we recommend to update to a newer {Cache} version” then you need to upgrade, or, if you’re not using it, remove it.

You are not required to use any caches, but caches improve server performance. See [Memory caching](#).

5.1.2 Transactional file locking is disabled

“Transactional file locking is disabled, this might lead to issues with race conditions.”

Please see [Transactional file locking](#) on how to correctly configure your environment for transactional file locking.

5.1.3 You are accessing this site via HTTP

“You are accessing this site via HTTP. We strongly suggest you configure your server to require using HTTPS instead.” Please take this warning seriously; using HTTPS is a fundamental security measure. You must configure your Web server to support it, and then there are some settings in the **Security** section of your Nextcloud Admin page to enable. The following pages describe how to enable HTTPS on the Apache and Nginx Web servers.

[Enabling SSL](#) (on Apache)

[Use HTTPS](#)

[NGINX configuration](#)

5.1.4 The test with getenv("PATH") only returns an empty response

Some environments are not passing a valid PATH variable to Nextcloud. The [php-fpm configuration notes](#) provides the information about how to configure your environment.

5.1.5 The “Strict-Transport-Security” HTTP header is not configured

“The “Strict-Transport-Security” HTTP header is not configured to least “15552000” seconds. For enhanced security we recommend enabling HSTS as described in our security tips.”

The HSTS header needs to be configured within your Web server by following the [Enable HTTP Strict Transport Security](#) documentation

5.1.6 /dev/urandom is not readable by PHP

“/dev/urandom is not readable by PHP which is highly discouraged for security reasons. Further information can be found in our documentation.”

This message is another one which needs to be taken seriously. Please have a look at the [Give PHP read access to /dev/urandom](#) documentation.

5.1.7 Your Web server is not yet set up properly to allow file synchronization

“Your web server is not yet set up properly to allow file synchronization because the WebDAV interface seems to be broken.”

At the ownCloud community forums a larger [FAQ](#) is maintained containing various information and debugging hints.

5.1.8 Outdated NSS / OpenSSL version

“cURL is using an outdated OpenSSL version (OpenSSL/\$version). Please update your operating system or features such as installing and updating apps via the app store or Federated Cloud Sharing will not work reliably.”

“cURL is using an outdated NSS version (NSS/\$version). Please update your operating system or features such as installing and updating apps via the app store or Federated Cloud Sharing will not work reliably.”

There are known bugs in older OpenSSL and NSS versions leading to misbehavior in combination with remote hosts using SNI. A technology used by most of the HTTPS websites. To ensure that Nextcloud will work properly you need to update OpenSSL to at least 1.0.2b or 1.0.1d. For NSS the patch version depends on your distribution and an heuristic is running the test which actually reproduces the bug. There are distributions such as RHEL/CentOS which have this backport still [pending](#).

5.1.9 Your Web server is not set up properly to resolve /.well-known/calDav/ or /.well-known/carddav/

Both URLs need to be correctly redirected to the DAV endpoint of Nextcloud. Please refer to [Service discovery](#) for more info.

5.1.10 Some files have not passed the integrity check

Please refer to the [Fixing invalid code integrity messages](#) documentation how to debug this issue.

5.1.11 Your database does not run with “READ COMMITTED” transaction isolation level

“Your database does not run with “READ COMMITTED” transaction isolation level. This can cause problems when multiple actions are executed in parallel.”

Please refer to [Database “READ COMMITTED” transaction isolation level](#) how to configure your database for this requirement.

5.2 Using the occ command

Nextcloud’s occ command (origins from “ownCloud Console”) is Nextcloud’s command-line interface. You can perform many common server operations with occ, such as installing and upgrading Nextcloud, manage users, encryption, passwords, LDAP setting, and more.

occ is in the `nextcloud/` directory; for example `/var/www/nextcloud` on Ubuntu Linux. occ is a PHP script. **You must run it as your HTTP user** to ensure that the correct permissions are maintained on your Nextcloud files and directories.

5.2.1 occ command Directory

- *Run occ as your HTTP user*
- *Apps commands*
- *Background jobs selector*
- *Config commands*
- *Dav commands*
- *Database conversion*
- *Add missing indices*
- *Encryption*
- *Federation sync*
- *File operations*
- *Files external*
- *Integrity check*
- *l10n, create JavaScript translation files for apps*
- *LDAP commands*
- *Logging commands*
- *Maintenance commands*
- *Security*
- *Trashbin*
- *User commands*
- *Group commands*
- *Versions*
- *Command line installation*
- *Command line upgrade*
- *Two-factor authentication*
- *Disable users*
- *Debugging*

5.2.2 Run occ as your HTTP user

The HTTP user is different on the various Linux distributions:

- The HTTP user and group in Debian/Ubuntu is www-data.
- The HTTP user and group in Fedora/CentOS is apache.
- The HTTP user and group in Arch Linux is http.
- The HTTP user in openSUSE is wwwrun, and the HTTP group is www.

If your HTTP server is configured to use a different PHP version than the default (/usr/bin/php), occ should be run with the same version. For example, in CentOS 6.5 with SCL-PHP70 installed, the command looks like this:

```
sudo -u apache /opt/rh/php70/root/usr/bin/php /var/www/html/nextcloud/occ
```

Note: Although the following examples make use of the `sudo -u ... /path/to/php /path/to/occ` method, your environment may require use of a different wrapper utility than `sudo` to execute the command as the appropriate user. Other common wrappers:

- `su --command '/path/to/php ...' username` – Note here that the target user specification comes at the end, and the command to execute is specified first.
- `runuser --user username -- /path/to/php ...` – This wrapper might be used in container contexts (ex: Docker / arm32v7/nextcloud) where both `sudo` and `su` wrapper utilities cannot be used.

Running `occ` with no options lists all commands and options, like this example on Ubuntu:

```
sudo -u www-data php occ
Nextcloud version 19.0.0

Usage:
  command [options] [arguments]

Options:
  -h, --help            Display this help message
  -q, --quiet           Do not output any message
  -V, --version         Display this application version
  --ansi               Force ANSI output
  --no-ansi            Disable ANSI output
  -n, --no-interaction  Do not ask any interactive question
  --no-warnings        Skip global warnings, show command output only
  -v|vv|vvv, --verbose Increase the verbosity of messages: 1 for normal output,
                        2 for more verbose output and 3 for debug

Available commands:
  check                check dependencies of the server
                       environment
  help                 Displays help for a command
  list                 Lists commands
  status               show some status information
  upgrade              run upgrade routines after installation of
                       a new release. The release has to be
                       installed before.
```

This is the same as `sudo -u www-data php occ list`.

Run it with the `-h` option for syntax help:

```
sudo -u www-data php occ -h
```

Display your Nextcloud version:

```
sudo -u www-data php occ -V
Nextcloud version 19.0.0
```

Query your Nextcloud server status:

```
sudo -u www-data php occ status
- installed: true
- version: 19.0.0.12
- versionstring: 19.0.0
- edition:
```

occ has options, commands, and arguments. Options and arguments are optional, while commands are required. The syntax is:

```
occ [options] command [arguments]
```

Get detailed information on individual commands with the `help` command, like this example for the `maintenance:mode` command:

```
sudo -u www-data php occ help maintenance:mode
Usage:
  maintenance:mode [options]

Options:
  --on           enable maintenance mode
  --off          disable maintenance mode
  -h, --help     Display this help message
  -q, --quiet    Do not output any message
  -V, --version  Display this application version
  --ansi         Force ANSI output
  --no-ansi      Disable ANSI output
  -n, --no-interaction Do not ask any interactive question
  --no-warnings  Skip global warnings, show command output only
  -v|vv|vvv, --verbose Increase the verbosity of messages: 1 for normal output,
                                     2 for more verbose output and 3 for debug
```

The status command from above has an option to define the output format. The default is plain text, but it can also be json:

```
sudo -u www-data php occ status --output=json
{"installed":true,"version":"19.0.0.9","versionstring":"19.0.0","edition":""}
```

or `json_pretty`:

```
sudo -u www-data php occ status --output=json_pretty
{
  "installed": true,
  "version": "19.0.0.12",
  "versionstring": "19.0.0",
  "edition": ""
}
```

This output option is available on all list and list-like commands: `status`, `check`, `app:list`, `config:list`, `encryption:status` and `encryption:list-modules`

5.2.3 Enabling autocompletion

Note: Command autocompletion currently only works if the user you use to execute the occ commands has a profile. `www-data` in most cases is `nologon` and therefor **cannot** use this feature.

Autocompletion is available for bash (and bash based consoles). To enable it, you have to run **one** of the following commands:

```
# BASH ~4.x, ZSH
source <(/var/www/html/nextcloud/occ _completion --generate-hook)

# BASH ~3.x, ZSH
/var/www/html/nextcloud/occ _completion --generate-hook | source /dev/stdin

# BASH (any version)
eval $(/var/www/html/nextcloud/occ _completion --generate-hook)
```

This will allow you to use autocompletion with the full path `/var/www/html/nextcloud/occ <tab>`.

If you also want to use autocompletion on occ from within the directory without using the full path, you need to specify `--program occ` after the `--generate-hook`.

If you want the completion to apply automatically for all new shell sessions, add the command to your shell's profile (eg. `~/.bash_profile` or `~/.zshrc`).

5.2.4 Apps commands

The app commands list, enable, and disable apps:

```
app
app:install      install selected app
app:disable      disable an app
app:enable       enable an app
app:getpath      get an absolute path to the app directory
app:list         list all available apps
app:update       update an app or all apps
app:remove       disable and remove an app
```

Download and install an app:

```
sudo -u www-data php occ app:install twofactor_totp
```

Install but don't enable:

```
sudo -u www-data php occ app:install --keep-disabled twofactor_totp
```

List all of your installed apps, and show whether they are enabled or disabled:

```
sudo -u www-data php occ app:list
```

Enable an app, for example the External Storage Support app:

```
sudo -u www-data php occ app:enable files_external
files_external enabled
```

Disable an app:

```
sudo -u www-data php occ app:disable files_external
files_external disabled
```

You can get the full filepath to an app:

```
sudo -u www-data php occ app:getpath notifications
/var/www/nextcloud/apps/notifications
```

To update an app, for instance Contacts:

```
sudo -u www-data php occ app:update contacts
```

To update all apps:

```
sudo -u www-data php occ app:update --all
```

5.2.5 Background jobs selector

Use the `background` command to select which scheduler you want to use for controlling background jobs, Ajax, Webcron, or Cron. This is the same as using the **Cron** section on your Nextcloud Admin page:

```
background
background:ajax      Use ajax to run background jobs
background:cron       Use cron to run background jobs
background:webcron    Use webcron to run background jobs
```

This example selects Ajax:

```
sudo -u www-data php occ background:ajax
Set mode for background jobs to 'ajax'
```

The other two commands are:

- `background:cron`
- `background:webcron`

See *Background jobs* to learn more.

5.2.6 Config commands

The config commands are used to configure the Nextcloud server:

```
config
config:app:delete      Delete an app config value
config:app:get          Get an app config value
config:app:set          Set an app config value
config:import           Import a list of configs
config:list             List all configs
config:system:delete    Delete a system config value
config:system:get       Get a system config value
config:system:set       Set a system config value
```

You can list all configuration values with one command:

```
sudo -u www-data php occ config:list
```

By default, passwords and other sensitive data are omitted from the report, so the output can be posted publicly (e.g. as part of a bug report). In order to generate a full backport of all configuration values the `--private` flag needs to be set:

```
sudo -u www-data php occ config:list --private
```

The exported content can also be imported again to allow the fast setup of similar instances. The import command will only add or update values. Values that exist in the current configuration, but not in the one that is being imported are left untouched:

```
sudo -u www-data php occ config:import filename.json
```

It is also possible to import remote files, by piping the input:

```
sudo -u www-data php occ config:import < local-backup.json
```

Note: While it is possible to update/set/delete the versions and installation statuses of apps and Nextcloud itself, it is **not** recommended to do this directly. Use the `occ app:enable`, `occ app:disable` and `occ app:update` commands instead.

Getting a single configuration value

These commands get the value of a single app or system configuration:

```
sudo -u www-data php occ config:system:get version
19.0.0.12

sudo -u www-data php occ config:app:get activity installed_version
2.2.1
```

Setting a single configuration value

These commands set the value of a single app or system configuration:

```
sudo -u www-data php occ config:system:set logtimezone
--value="Europe/Berlin"
System config value logtimezone set to Europe/Berlin

sudo -u www-data php occ config:app:set files_sharing
incoming_server2server_share_enabled --value="yes" --type=boolean
Config value incoming_server2server_share_enabled for app files_sharing set to yes
```

The `config:system:set` command creates the value, if it does not already exist. To update an existing value, set `--update-only`:

```
sudo -u www-data php occ config:system:set doesnotexist --value="true"
--type=boolean --update-only
Value not updated, as it has not been set before.
```

Note that in order to write a Boolean, float, or integer value to the configuration file, you need to specify the type on your command. This applies only to the `config:system:set` command. The following values are known:

- boolean
- integer
- float
- string (default)

When you want to e.g. disable the maintenance mode run the following command:

```
sudo -u www-data php occ config:system:set maintenance --value=false
--type=boolean
Nextcloud is in maintenance mode - no app have been loaded
System config value maintenance set to boolean false
```

Setting an array configuration value

Some configurations (e.g. the trusted domain setting) are an array of data. In this case, `config:system:get` for this key will return multiple values:

```
sudo -u www-data php occ config:system:get trusted_domains
localhost
nextcloud.local
sample.tld
```

To set one of multiple values, you need to specify the array index as the second name in the `config:system:set` command, separated by a space. For example, to replace `sample.tld` with `example.com`, `trusted_domains => 2` needs to be set:

```
sudo -u www-data php occ config:system:set trusted_domains 2
--value=example.com
System config value trusted_domains => 2 set to string example.com

sudo -u www-data php occ config:system:get trusted_domains
localhost
nextcloud.local
example.com
```

Setting a hierarchical configuration value

Some configurations use hierarchical data. For example, the settings for the Redis cache would look like this in the `config.php` file:

```
'redis' => array(
    'host' => '/var/run/redis/redis.sock',
    'port' => 0,
    'dbindex' => 0,
    'password' => 'secret',
    'timeout' => 1.5,
)
```

Setting such hierarchical values works similarly to setting an array value above. For this Redis example, use the following commands:

```
sudo -u www-data php occ config:system:set redis host \
--value=/var/run/redis/redis.sock
sudo -u www-data php occ config:system:set redis port --value=0
sudo -u www-data php occ config:system:set redis dbindex --value=0
sudo -u www-data php occ config:system:set redis password --value=secret
sudo -u www-data php occ config:system:set redis timeout --value=1.5
```

Deleting a single configuration value

These commands delete the configuration of an app or system configuration:

```
sudo -u www-data php occ config:system:delete maintenance:mode
System config value maintenance:mode deleted

sudo -u www-data php occ config:app:delete appname provisioning_api
Config value provisioning_api of app appname deleted
```

The delete command will by default not complain if the configuration was not set before. If you want to be notified in that case, set the `--error-if-not-exists` flag:

```
sudo -u www-data php occ config:system:delete doesnotexist
--error-if-not-exists
Config provisioning_api of app appname could not be deleted because it did not exist
```

5.2.7 Dav commands

A set of commands to create and manage addressbooks and calendars:

```
dav
dav:create-addressbook      Create a dav addressbook
dav:create-calendar         Create a dav calendar
dav:list-calendars          List all calendars of a user
dav:move-calendar           Move a calendar from a user to another
dav:remove-invalid-shares   Remove invalid dav shares
dav:send-event-reminders    Sends event reminders
```

(continues on next page)

(continued from previous page)

<code>dav:sync-birthday-calendar</code>	Synchronizes the birthday calendar
<code>dav:sync-system-addressbook</code>	Synchronizes users to the system addressbook

The syntax for `dav:create-addressbook` and `dav:create-calendar` is `dav:create-addressbook [user] [name]`. This example creates the addressbook `mollybook` for the user `molly`:

```
sudo -u www-data php occ dav:create-addressbook molly mollybook
```

This example creates a new calendar for `molly`:

```
sudo -u www-data php occ dav:create-calendar molly mollycal
```

`Molly` will immediately see these in the Calendar and Contacts apps.

`dav:lists-calendars [user]` will display a table listing the calendars for a given user. This example will list all calendars for user `annie`:

```
sudo -u www-data php occ dav:list-calendars annie
```

`dav::move-calendar [name] [sourceuid] [destinationuid]` allows the admin to move a calendar named `name` from a user `sourceuid` to the user `destinationuid`. You can use the force option `-f` to enforce the move if there are conflicts with existing shares. The system will also generate a new unique calendar name in case there is a conflict over the destination user.

This example will move calendar named `personal` from user `dennis` to user `sabine`:

```
sudo -u www-data php occ dav:move-calendar personal dennis sabine
```

`dav:remove-invalid-shares` will remove invalid shares created by a bug into the calendar app

`dav:send-event-reminders` is a command that should be called regularly through a dedicated cron job to send event reminder notifications.

See [Calendar](#) for more information on how to use this command.

`dav:sync-birthday-calendar` adds all birthdays to your calendar from addressbooks shared with you. This example syncs to your calendar from user `bernie`:

```
sudo -u www-data php occ dav:sync-birthday-calendar bernie
```

`dav:sync-system-addressbook` synchronizes all users to the system addressbook:

```
sudo -u www-data php occ dav:sync-system-addressbook
```

5.2.8 Database conversion

The SQLite database is good for testing, and for Nextcloud servers with small single-user workloads that do not use sync clients, but production servers with multiple users should use MariaDB, MySQL, or PostgreSQL. You can use `occ` to convert from SQLite to one of these other databases.

<code>db</code>	
<code>db:convert-type</code>	Convert the Nextcloud database to the newly configured one

(continues on next page)

(continued from previous page)

```
db:generate-change-script generates the change script from the current
                           connected db to db_structure.xml
```

You need:

- Your desired database and its PHP connector installed.
- The login and password of a database admin user.
- The database port number, if it is a non-standard port.

This is example converts SQLite to MySQL/MariaDB:

```
sudo -u www-data php occ db:convert-type mysql oc_dbuser 127.0.0.1
oc_database
```

For a more detailed explanation see *Converting database type*

5.2.9 Add missing indices

It might happen that we add from time to time new indices to already existing database tables, for example to improve performance. In order to check your database for missing indices run following command:

```
sudo -u www-data php occ db:add-missing-indices
```

5.2.10 Encryption

occ includes a complete set of commands for managing encryption:

encryption	
encryption:change-key-storage-root	Change key storage root
encryption:decrypt-all	Disable server-side encryption and decrypt all files
encryption:disable	Disable encryption
encryption:enable	Enable encryption
encryption:enable-master-key	Enable the master key. Only available for fresh installations with no existing encrypted data! There is also no way to disable it again.
encryption:encrypt-all	Encrypt all files for all users
encryption:list-modules	List all available encryption modules
encryption:set-default-module	Set the encryption default module
encryption:show-key-storage-root	Show current key storage root
encryption:status	Lists the current status of encryption

encryption:status shows whether you have active encryption, and your default encryption module. To enable encryption you must first enable the Encryption app, and then run encryption:enable:

```
sudo -u www-data php occ app:enable encryption
sudo -u www-data php occ encryption:enable
sudo -u www-data php occ encryption:status
- enabled: true
- defaultModule: OC_DEFAULT_MODULE
```

`encryption:change-key-storage-root` is for moving your encryption keys to a different folder. It takes one argument, `newRoot`, which defines your new root folder:

```
sudo -u www-data php occ encryption:change-key-storage-root /etc/oc-keys
```

You can see the current location of your keys folder:

```
sudo -u www-data php occ encryption:show-key-storage-root  
Current key storage root: default storage location (data/)
```

`encryption:list-modules` displays your available encryption modules. You will see a list of modules only if you have enabled the Encryption app. Use `encryption:set-default-module [module name]` to set your desired module.

`encryption:encrypt-all` encrypts all data files for all users. You must first put your Nextcloud server into *maintenance mode* to prevent any user activity until encryption is completed.

`encryption:decrypt-all` decrypts all user data files, or optionally a single user:

```
sudo -u www-data php occ encryption:decrypt freda
```

Users must have enabled recovery keys on their Personal pages. You must first put your Nextcloud server into *maintenance mode* to prevent any user activity until decryption is completed.

Note that if you do not have master key/recovery key enabled, you can ONLY decrypt files per user, one user at a time and NOT when in maintenance mode. You will need the users' password to decrypt the files.

Use `encryption:disable` to disable your encryption module. You must first put your Nextcloud server into *maintenance mode* to prevent any user activity.

`encryption:enable-master-key` creates a new master key, which is used for all user data instead of individual user keys. This is especially useful to enable single-sign on. Use this only on fresh installations with no existing data, or on systems where encryption has not already been enabled. It is not possible to disable it.

See *Encryption configuration* to learn more.

5.2.11 Federation sync

Note: This command is only available when the “Federation” app (`federation`) is enabled.

Synchronize the addressbooks of all federated Nextcloud servers:

```
federation:sync-addressbooks Synchronizes addressbooks of all  
                             federated clouds
```

In Nextcloud, servers connected with federation shares can share user address books, and auto-complete usernames in share dialogs. Use this command to synchronize federated servers:

```
sudo -u www-data php occ federation:sync-addressbooks
```

5.2.12 File operations

occ has three commands for managing files in Nextcloud:

```
files
files:cleanup          cleanup filecache
files:scan             rescan filesystem
files:scan-app-data    rescan the AppData folder
files:transfer-ownership All files' and folders' ownerships are moved to another
                        user. Outgoing shares are moved as well.
                        Incoming shares are not moved because the sharing user
                        holds the ownership of the respective files and therefore
                        owns the decision which actual users/groups to be shared.
↳ with.
```

Scan

The `files:scan` command scans for new files and updates the file cache. You may rescan all files, per-user, a space-delimited list of users, and limit the search path. If not using `--quiet`, statistics will be shown at the end of the scan:

```
sudo -u www-data php occ files:scan --help
Usage:
files:scan [-p|--path="..."] [-q|--quiet] [-v|vv|vvv --verbose] [--all]
[user_id1] ... [user_idN]

Arguments:
user_id          will rescan all files of the given user(s)

Options:
--path          limit rescan to the user/path given
--all           will rescan all files of all known users
--quiet         suppress any output
--verbose       files and directories being processed are shown
                  additionally during scanning
--unscanned     scan only previously unscanned files
```

Verbosity levels of `-vv` or `-vvv` are automatically reset to `-v`

Note for option `--unscanned`: In general there is a background job (through cron) that will do that scan periodically. The `--unscanned` option makes it possible to trigger this from the CLI.

When using the `--path` option, the path must consist of following components:

```
"user_id/files/path"
or
"user_id/files/mount_name"
or
"user_id/files/mount_name/path"
```

where the term `files` is mandatory.

Example:

```
--path="/alice/files/Music"
```

In the example above, the `user_id` `alice` is determined implicitly from the path component given.

The `--path`, `--all` and `[user_id]` parameters are exclusive - only one must be specified.

Scan appdata

Appdata is a folder inside of the data directory which contains files that are shared between users and can be put there by the server or apps like avatar images, file previews and cached CSS files for example.

Since the regular files scan only operates on user files the `occ files:scan-app-data` command will check the appdata directory and make sure that the filecache is consistent with the files on the actual storage.:

Usage:

```
files:scan-app-data [options] [--] [<folder>]
```

Arguments:

```
folder                The appdata subfolder to scan [default: ""]
```

Cleanup

`files:cleanup` tidies up the server's file cache by deleting all file entries that have no matching entries in the storage table.

Transfer

You may transfer all files and shares from one user to another. This is useful before removing a user:

```
sudo -u www-data php occ files:transfer-ownership <source-user> <destination-user>
```

It is also possible to transfer only one directory along with it's contents. This can be useful to restructure your organization or quotas. The `--path` argument is given as the path to the directory as seen from the source user:

```
sudo -u www-data php occ files:transfer-ownership --path="path_to_dir" <source-user>
↳<destination-user>
```

Users may also transfer files or folders selectively by themselves. See [user documentation](#) for details.

5.2.13 Files Sharing

Commands for handling shares:

sharing

```
sharing:cleanup-remote-storages Cleanup shared storage entries that have no matching_
↳entry in the shares_external table
```

```
sharing:expiration-notification Notify share initiators when a share will expire the_
↳next day
```

5.2.14 Files external

Note: These commands are only available when the “External storage support” app (files_external) is enabled.

Commands for managing external storage:

files_external	
files_external:applicable	Manage applicable users and groups for a mount
files_external:backends	Show available authentication and storage backends
files_external:config	Manage backend configuration for a mount
files_external:create	Create a new mount configuration
files_external:delete	Delete an external mount
files_external:export	Export mount configurations
files_external:import	Import mount configurations
files_external:list	List configured mounts
files_external:option	Manage mount options for a mount
files_external:verify	Verify mount configuration
files_external:notify	Listen for active update notifications for a configured_
↪external mount	

These commands replicate the functionality in the Nextcloud Web GUI, plus two new features: files_external:export and files_external:import.

Use files_external:export to export all admin mounts to stdout, and files_external:export [user_id] to export the mounts of the specified Nextcloud user.

Use files_external:import [filename] to import legacy JSON configurations, and to copy external mount configurations to another Nextcloud server.

5.2.15 Integrity check

Apps which have a Featured tag **MUST** be code signed with Nextcloud. Unsigned featured apps won't be installable anymore. Code signing is optional for all third-party applications:

integrity	
integrity:check-app	Check app integrity using a signature.
integrity:check-core	Check core integrity using a signature.
integrity:sign-app	Signs an app using a private key.
integrity:sign-core	Sign core using a private key

After creating your signing key, sign your app like this example:

```
sudo -u www-data php occ integrity:sign-app --privateKey=/Users/lukasreschke/contacts.
↪key --certificate=/Users/lukasreschke/CA/contacts.crt --path=/Users/lukasreschke/
↪Programming/contacts
```

Verify your app:

```
sudo -u www-data php occ integrity:check-app --path=/pathto/app appname
```

When it returns nothing, your app is signed correctly. When it returns a message then there is an error. See [Code Signing](#) in the Developer manual for more detailed information.

integrity:sign-core is for Nextcloud core developers only.

See *Code signing* to learn more.

5.2.16 l10n, create JavaScript translation files for apps

This command is for app developers to update their translation mechanism from ownCloud 7 to Nextcloud.

5.2.17 LDAP commands

Note: These commands are only available when the “LDAP user and group backend” app (user_ldap) is enabled.

These LDAP commands appear only when you have enabled the LDAP app. Then you can run the following LDAP commands with occ:

ldap	
ldap:check-user	checks whether a user exists on LDAP.
ldap:create-empty-config	creates an empty LDAP configuration
ldap:delete-config	deletes an existing LDAP configuration
ldap:search	executes a user or group search
ldap:set-config	modifies an LDAP configuration
ldap:show-config	shows the LDAP configuration
ldap:show-remnants	shows which users are not available on LDAP anymore, but have remnants in Nextcloud.
ldap:test-config	tests an LDAP configuration

Search for an LDAP user, using this syntax:

```
sudo -u www-data php occ ldap:search [--group] [--offset="..."]  
[--limit="..."] search
```

Searches will match at the beginning of the attribute value only. This example searches for givenNames that start with “rob”:

```
sudo -u www-data php occ ldap:search "rob"
```

This will find robbie, roberta, and robin. Broaden the search to find, for example, jeroboam with the asterisk wildcard:

```
sudo -u www-data php occ ldap:search "*rob"
```

User search attributes are set with `ldap:set-config` (below). For example, if your search attributes are `givenName` and `sn` you can find users by first name + last name very quickly. For example, you’ll find Terri Hanson by searching for `te ha`. Trailing whitespaces are ignored.

Check if an LDAP user exists. This works only if the Nextcloud server is connected to an LDAP server:

```
sudo -u www-data php occ ldap:check-user robert
```

`ldap:check-user` will not run a check when it finds a disabled LDAP connection. This prevents users that exist on disabled LDAP connections from being marked as deleted. If you know for certain that the user you are searching for is not in one of the disabled connections, and exists on an active connection, use the `--force` option to force it to check all active LDAP connections:

```
sudo -u www-data php occ ldap:check-user --force robert
```

ldap:create-empty-config creates an empty LDAP configuration. The first one you create has no configID, like this example:

```
sudo -u www-data php occ ldap:create-empty-config
Created new configuration with configID ''
```

This is a holdover from the early days, when there was no option to create additional configurations. The second, and all subsequent, configurations that you create are automatically assigned IDs:

```
sudo -u www-data php occ ldap:create-empty-config
Created new configuration with configID 's01'
```

Then you can list and view your configurations:

```
sudo -u www-data php occ ldap:show-config
```

And view the configuration for a single configID:

```
sudo -u www-data php occ ldap:show-config s01
```

ldap:delete-config [configID] deletes an existing LDAP configuration:

```
sudo -u www-data php occ ldap:delete s01
Deleted configuration with configID 's01'
```

The ldap:set-config command is for manipulating configurations, like this example that sets search attributes:

```
sudo -u www-data php occ ldap:set-config s01 ldapAttributesForUserSearch
"cn;givenname;sn;displayname;mail"
```

ldap:test-config tests whether your configuration is correct and can bind to the server:

```
sudo -u www-data php occ ldap:test-config s01
The configuration is valid and the connection could be established!
```

ldap:show-remnants is for cleaning up the LDAP mappings table, and is documented in [LDAP user cleanup](#).

5.2.18 Logging commands

These commands view and configure your Nextcloud logging preferences:

```
log
log:file      manipulate Nextcloud logging backend
log:manage    manage logging configuration
log:tail      tail the nextcloud logfile [requires app "Log Reader" to be enabled]
log:watch     watch the nextcloud logfile live [requires app "Log Reader" to be
↪enabled]
```

Run log:file [--] [--enable] [--file] [--rotate-size] to see your current logging status:

```
sudo -u www-data php occ log:file
Log backend Nextcloud: enabled
Log file: /opt/nextcloud/data/nextcloud.log
Rotate at: disabled
```

- `--enable` turns on logging.
- `--file` sets a different log file path.
- `--rotate-size` sets your rotation by log file size in bytes with; 0 disables rotation.

`log:manage [--backend] [--level] [--timezone]` sets your logging backend, log level, and timezone. The defaults are file, warning, and UTC. Available options are:

- `--backend` [file, syslog, errorlog, systemd]
- `--level` [debug|info|warning|error|fatal]
- `--timezone` according to <https://www.php.net/manual/en/timezones.php>

5.2.19 Maintenance commands

Use these commands when you upgrade Nextcloud, manage encryption, perform backups and other tasks that require locking users out until you are finished:

```
maintenance
maintenance:data-fingerprint      update the systems data-fingerprint after a backup,
↪ is restored
maintenance:mimetype:update-db    Update database mimetypes and update filecache
maintenance:mimetype:update-js    Update mimetypeelist.js
maintenance:mode                  set maintenance mode
maintenance:repair                 repair this installation
maintenance:theme:update           Apply custom theme changes
maintenance:update:htaccess        Updates the .htaccess file
```

`maintenance:mode` locks the sessions of all logged-in users, including administrators, and displays a status screen warning that the server is in maintenance mode. Users who are not already logged in cannot log in until maintenance mode is turned off. When you take the server out of maintenance mode logged-in users must refresh their Web browsers to continue working:

```
sudo -u www-data php occ maintenance:mode --on
sudo -u www-data php occ maintenance:mode --off
```

After restoring a backup of your data directory or the database, you should always call `maintenance:data-fingerprint` once. This changes the ETag for all files in the communication with sync clients, allowing them to realize a file was modified.

The `maintenance:repair` command runs automatically during upgrades to clean up the database, so while you can run it manually there usually isn't a need to:

```
sudo -u www-data php occ maintenance:repair
```

`maintenance:mimetype:update-db` updates the Nextcloud database and file cache with changed mimetypes found in `config/mimetyperemapping.json`. Run this command after modifying `config/mimetyperemapping.json`. If you change a mimetype, run `maintenance:mimetype:update-db --repair-filecache` to apply the change to existing files.

Run the `maintenance:theme:update` command if the icons of your custom theme are not updated correctly. This updates the `mimetypeslist.js` and clears the image cache.

5.2.20 Security

Use these commands to manage server-wide SSL certificates. These are useful when you create federation shares with other Nextcloud servers that use self-signed certificates:

```
security
security:certificates      list trusted certificates
security:certificates:import import trusted certificate
security:certificates:remove remove trusted certificate
```

This example lists your installed certificates:

```
sudo -u www-data php occ security:certificates
```

Import a new certificate:

```
sudo -u www-data php occ security:import /path/to/certificate
```

Remove a certificate:

```
sudo -u www-data php occ security:remove [certificate name]
```

5.2.21 Trashbin

Note: This command is only available when the “Deleted files” app (`files_trashbin`) is enabled.

The `trashbin:cleanup [--all-users] [--] [<user_id>...]` command removes the deleted files of the specified users in a space-delimited list, or all users if `--all-users` is specified.

```
trashbin
trashbin:cleanup  [--all-users] [--] [<user_id>...]  Remove deleted files
```

This example removes the deleted files of all users:

```
sudo -u www-data php occ trashbin:cleanup --all-users
Remove all deleted files for all users
Remove deleted files for users on backend Database
freda
molly
stash
rosa
edward
```

This example removes the deleted files of users molly and freda:

```
sudo -u www-data php occ trashbin:cleanup molly freda
Remove deleted files of molly
Remove deleted files of freda
```

5.2.22 User commands

The `user` commands create and remove users, reset passwords, display a simple report showing how many users you have, and when a user was last logged in:

<code>user</code>	
<code>user:add</code>	adds a user
<code>user:delete</code>	deletes the specified user
<code>user:disable</code>	disables the specified user
<code>user:enable</code>	enables the specified user
<code>user:lastseen</code>	shows when the user was logged in last time
<code>user:list</code>	shows list of all registered users
<code>user:report</code>	shows how many users have access
<code>user:resetpassword</code>	Resets the password of the named user
<code>user:setting</code>	Read and modify user settings

You can create a new user with their display name, login name, and any group memberships with the `user:add` command. The syntax is:

```
user:add [--password-from-env] [--display-name=["..."]] [-g|--group=["..."]]
uid
```

The `display-name` corresponds to the **Full Name** on the Users page in your Nextcloud Web UI, and the `uid` is their **Username**, which is their login name. This example adds new user Layla Smith, and adds them to the **users** and **db-admins** groups. Any groups that do not exist are created:

```
sudo -u www-data php occ user:add --display-name="Layla Smith"
--group="users" --group="db-admins" layla
Enter password:
Confirm password:
The user "layla" was created successfully
Display name set to "Layla Smith"
User "layla" added to group "users"
User "layla" added to group "db-admins"
```

Go to your Users page, and you will see your new user.

`password-from-env` allows you to set the user's password from an environment variable. This prevents the password from being exposed to all users via the process list, and will only be visible in the history of the user (root) running the command. This also permits creating scripts for adding multiple new users.

To use `password-from-env` you must run as “real” root, rather than `sudo`, because `sudo` strips environment variables. This example adds new user Fred Jones:

```
export OC_PASS=newpassword
su -s /bin/sh www-data -c 'php occ user:add --password-from-env
--display-name="Fred Jones" --group="users" fred'
The user "fred" was created successfully
Display name set to "Fred Jones"
User "fred" added to group "users"
```

You can reset any user's password, including administrators (see *Resetting a lost admin password*):

```
sudo -u www-data php occ user:resetpassword layla
Enter a new password:
```

(continues on next page)

(continued from previous page)

```
Confirm the new password:
Successfully reset password for layla
```

You may also use `password-from-env` to reset passwords:

```
export OC_PASS=newpassword
su -s /bin/sh www-data -c 'php occ user:resetpassword --password-from-env
  layla'
Successfully reset password for layla
```

You can delete users:

```
sudo -u www-data php occ user:delete fred
```

View a user's most recent login:

```
sudo -u www-data php occ user:lastseen layla
  layla's last login: 09.01.2020 18:46
```

Read user settings:

```
sudo -u www-data php occ user:setting layla
- core:
- lang: en
- login:
- lastLogin: 1465910968
- settings:
- email: layla@example.tld
```

Filter by app:

```
sudo -u www-data php occ user:setting layla core
- core:
- lang: en
```

Get a single setting:

```
sudo -u www-data php occ user:setting layla core lang
en
```

Set a setting:

```
sudo -u www-data php occ user:setting layla settings email "new-layla@example.tld"
```

Delete a setting:

```
sudo -u www-data php occ user:setting layla settings email --delete
```

Generate a simple report that counts all users, including users on external user authentication servers such as LDAP:

```
sudo -u www-data php occ user:report
+-----+-----+
| User Report | |
+-----+-----+
```

(continues on next page)

(continued from previous page)

Database	12
LDAP	86
total users	98
user directories	2
+-----+	+-----+

5.2.23 Group commands

The group commands create and remove groups, add and remove users in groups, display a list of all users in a group:

group	
group:add	add a group
group:delete	remove a group
group:adduser	add a user to a group
group:removeuser	remove a user from a group
group:list	list configured groups

You can create a new group with the `group:add` command. The syntax is:

```
group:add [gid]
```

The `gid` corresponds to the group name you entering after clicking “Add group” on the Users page in your Nextcloud Web UI. This example adds new group “beer”:

```
sudo -u www-data php occ group:add beer
```

Add an existing user to the specified group with the `group:adduser` command. The syntax is:

```
group:adduser [gid] [uid]
```

This example adds the user “denis” to the existing group “beer”:

```
sudo -u www-data php occ group:adduser beer denis
```

You can remove user from the group with the `group:removeuser` command. This example removes the existing user “denis” from the existing group “beer”:

```
sudo -u www-data php occ group:removeuser beer denis
```

Remove a group with the `group:delete` command. Removing a group doesn’t remove users in a group. You cannot remove the “admin” group. This example removes the existing group “beer”:

```
sudo -u www-data php occ group:delete beer
```

List configured groups via the `group:list` command. The syntax is:

```
group:list [-l|--limit] [-o|--offset] [--output="..."]
```

`limit` allows you to specify the number of groups to retrieve.

`offset` is an offset for retrieving groups.

output specifies the output format (plain, json or json_pretty). Default is plain.

5.2.24 Versions

Note: This command is only available when the “Versions” app (files_versions) is enabled.

Use this command to delete file versions for specific users, or for all users when none are specified:

```
versions
versions:cleanup    Delete versions
```

This example deletes all versions for all users:

```
sudo -u www-data php occ versions:cleanup
Delete all versions
Delete versions for users on backend Database
  freda
  molly
  stash
  rosa
  edward
```

You can delete versions for specific users in a space-delimited list:

```
sudo -u www-data php occ versions:cleanup freda molly
Delete versions of  freda
Delete versions of  molly
```

5.2.25 Command line installation

These commands are available only after you have downloaded and unpacked the Nextcloud archive, and taken no further installation steps.

You can install Nextcloud entirely from the command line. After downloading the tarball and copying Nextcloud into the appropriate directories you can use occ commands in place of running the graphical Installation Wizard.

Then choose your occ options. This lists your available options:

```
sudo -u www-data php /var/www/nextcloud/occ
Nextcloud is not installed - only a limited number of commands are available
Nextcloud version 19.0.0

Usage:
[options] command [arguments]

Options:
--help (-h)           Display this help message
--quiet (-q)          Do not output any message
--verbose (-v|vv|vvv) Increase the verbosity of messages: 1 for normal
output, 2 for more verbose output and 3 for debug
--version (-V)        Display this application version
```

(continues on next page)

(continued from previous page)

```
--ansi           Force ANSI output
--no-ansi        Disable ANSI output
--no-interaction (-n) Do not ask any interactive question
```

Available commands:

```
check           check dependencies of the server environment
help            Displays help for a command
list            Lists commands
status          show some status information
app
l10n
l10n:createjs   Create javascript translation files for a given app
maintenance
maintenance:install  install Nextcloud
```

Display your maintenance:install options:

```
sudo -u www-data php occ help maintenance:install
Nextcloud is not installed - only a limited number of commands are available
Usage:
maintenance:install [--database="..."] [--database-name="..."]
[--database-host="..."] [--database-user="..."] [--database-pass[="..."]]
[--database-table-prefix[="..."]] [--admin-user="..."] [--admin-pass="..."]
[--data-dir="..."]
```

Options:

```
--database       Supported database type (default: "sqlite")
--database-name  Name of the database
--database-host  Hostname of the database (default: "localhost")
--database-user  User name to connect to the database
--database-pass  Password of the database user
--admin-user     User name of the admin account (default: "admin")
--admin-pass     Password of the admin account
--data-dir       Path to data directory (default:
"/var/www/nextcloud/data")
--help (-h)      Display this help message
--quiet (-q)     Do not output any message
--verbose (-v|vv|vvv) Increase the verbosity of messages: 1 for normal
output, 2 for more verbose output and 3 for debug
--version (-V)   Display this application version
--ansi          Force ANSI output
--no-ansi        Disable ANSI output
--no-interaction (-n) Do not ask any interactive question
```

This example completes the installation:

```
cd /var/www/nextcloud/
sudo -u www-data php occ maintenance:install --database
"mysql" --database-name "nextcloud" --database-user "root" --database-pass
"password" --admin-user "admin" --admin-pass "password"
Nextcloud is not installed - only a limited number of commands are available
Nextcloud was successfully installed
```

Supported databases are:

- sqlite (SQLite3 - Nextcloud Community edition only)
- mysql (MySQL/MariaDB)
- pgsql (PostgreSQL)
- oci (Oracle - Nextcloud Enterprise edition only)

5.2.26 Command line upgrade

These commands are available only after you have downloaded upgraded packages or tar archives, and before you complete the upgrade.

List all options, like this example on CentOS Linux:

```
sudo -u apache php occ upgrade -h
Usage:
upgrade [--quiet]

Options:
--help (-h)           Display this help message.
--quiet (-q)          Do not output any message.
--verbose (-v|vv|vvv) Increase the verbosity of messages: 1 for normal output,
                      2 for more verbose output and 3 for debug.
--version (-V)        Display this application version.
--ansi                Force ANSI output.
--no-ansi             Disable ANSI output.
--no-interaction (-n) Do not ask any interactive question
```

When you are performing an update or upgrade on your Nextcloud server (see the Maintenance section of this manual), it is better to use occ to perform the database upgrade step, rather than the Web GUI, in order to avoid timeouts. PHP scripts invoked from the Web interface are limited to 3600 seconds. In larger environments this may not be enough, leaving the system in an inconsistent state. After performing all the preliminary steps (see [How to upgrade](#)) use this command to upgrade your databases, like this example on CentOS Linux. Note how it details the steps:

```
sudo -u www-data php occ upgrade
Nextcloud or one of the apps require upgrade - only a limited number of
commands are available
Turned on maintenance mode
Checked database schema update
Checked database schema update for apps
Updated database
Updating <gallery> ...
Updated <gallery> to 0.6.1
Updating <activity> ...
Updated <activity> to 2.1.0
Update successful
Turned off maintenance mode
```

Enabling verbosity displays timestamps:

```
sudo -u www-data php occ upgrade -v
Nextcloud or one of the apps require upgrade - only a limited number of commands are
↪available
```

(continues on next page)

(continued from previous page)

```
2015-06-23T09:06:15+0000 Turned on maintenance mode
2015-06-23T09:06:15+0000 Checked database schema update
2015-06-23T09:06:15+0000 Checked database schema update for apps
2015-06-23T09:06:15+0000 Updated database
2015-06-23T09:06:15+0000 Updated <files_sharing> to 0.6.6
2015-06-23T09:06:15+0000 Update successful
2015-06-23T09:06:15+0000 Turned off maintenance mode
```

If there is an error it throws an exception, and the error is detailed in your Nextcloud logfile, so you can use the log output to figure out what went wrong, or to use in a bug report:

```
Turned on maintenance mode
Checked database schema update
Checked database schema update for apps
Updated database
Updating <files_sharing> ...
Exception
ServerNotAvailableException: LDAP server is not available
Update failed
Turned off maintenance mode
```

5.2.27 Two-factor authentication

If a two-factor provider app is enabled, it is enabled for all users by default (though the provider can decide whether or not the user has to pass the challenge). In the case of a user losing access to the second factor (e.g. lost phone with two-factor SMS verification), the admin can try to disable the two-factor check for that user via the occ command:

```
sudo -u www-data php occ twofactor:disable <uid> <provider_id>
```

Note: This is not supported by all providers. For those that don't support this operation, the [Two-Factor Admin Support app](#) should be used where users get a one-time code to log into their account.

To re-enable two-factor auth again use the following command:

```
sudo -u www-data php occ twofactor:enable <uid> <provider_id>
```

Note: This is not supported by all providers. For those that don't support this operation, the [Two-Factor Admin Support app](#) should be used where users get a one-time code to log into their account.

5.2.28 Disable users

Admins can disable users via the occ command too:

```
sudo -u www-data php occ user:disable <username>
```

Use the following command to enable the user again:

```
sudo -u www-data php occ user:enable <username>
```

Note that once users are disabled, their connected browsers will be disconnected.

5.2.29 Debugging

In certain situations it's necessary to generate debugging information, e.g. before submitting a bug report. You can run occ with debug logging:

```
sudo -u www-data NC_loglevel=0 php occ -h
```

5.3 Activity app

You can configure your Nextcloud server to automatically send out e-mail notifications to your users for various events like:

- A file or folder has been shared
- A new file or folder has been created
- A file or folder has been changed
- A file or folder has been deleted

Users can see actions (delete, add, modify) that happen to files they have access to. Sharing actions are only visible to the sharer and sharee.

5.3.1 Enabling the activity app

The Activity App is shipped and enabled by default. If it is not enabled simply go to your Nextcloud Apps page to enable it.

5.3.2 Configuring your Nextcloud for the activity app

To configure your Nextcloud to send out e-mail notifications a working *Email* is mandatory.

Furthermore it is recommended to configure the background job Webcron or Cron as described in *Background jobs*.

There is also a configuration option `activity_expire_days` available in your `config.php` (See *Activity app*) which allows you to clean-up older activities from the database.

5.3.3 Activities in groupfolders

By default activities in groupfolders are only generated for the current user. This is due to the logic of groupfolders. There is a config flag `activity_use_cached_mountpoints` that makes activities in groupfolders work like in normal shares when set to `true`.

Warning: This config option comes with the following limitations:

1. Users that had access to a groupfolder, share or external storage can see activities in their stream and emails that happen after they are removed until they login again
2. Users that are newly added to a groupfolder, share or external storage can not see activities in their stream nor emails that happen after they are added until they login again

5.3.4 Better scheduling of activity emails

In certain scenarios it makes sense to send the activity emails out more regularly, e.g. you want to send the hourly emails always at the full hour, daily emails before people start to work in the morning and weekly mails shall be send on monday morning, so people can read up when starting into the week.

A console command is available to trigger sending those emails. This allows to set up special cron jobs on your server with the known granularity, instead of relying on the Nextcloud cron feature which is not very flexible on scheduling.

To implement the samples mentioned above, the following three entries are necessary:

```
# crontab -u www-data -e
0 * * * * php -f /var/www/nextcloud/occ activity:send-mails hourly
30 7 * * * php -f /var/www/nextcloud/occ activity:send-mails daily
30 7 * * MON php -f /var/www/nextcloud/occ activity:send-mails weekly
```

If you want to manually send out all activity emails which are queued, you can run `occ activity:send-mails` without any argument.

5.4 Memory caching

You can significantly improve your Nextcloud server performance with memory caching, where frequently-requested objects are stored in memory for faster retrieval. There are two types of caches to use: a PHP opcode cache, which is commonly called *opcache*, and data caching for your Web server. If you do not install and enable a local memcache you will see a warning on your Nextcloud admin page. **A memcache is not required and you may safely ignore the warning if you prefer.**

Note: If you enable only a distributed cache in your `config.php` (`memcache.distributed`) and not a local cache (`memcache.local`) you will still see the cache warning.

A PHP opcode cache stores compiled PHP scripts so they don't need to be re-compiled every time they are called. PHP bundles the Zend OPcache in core since version 5.5, so you don't need to install an opcode cache manually.

Data caching is supplied by the user (APCu), Memcached or Redis.

Nextcloud supports multiple memory caching backends, so you can choose the type of memcache that best fits your needs. The supported caching backends are:

- **APCu, APCu 4.0.6 and up required.** A local cache for systems.

- **Redis, PHP module 2.2.6 and up required.** For local and distributed caching as well as transactional file locking.
- **Memcached** For distributed caching.

Memcaches must be explicitly configured in Nextcloud by installing and enabling your desired cache, and then adding the appropriate entry to `config.php` (See [Configuration Parameters](#) for an overview of all possible config parameters).

You may use both a local and a distributed cache. Recommended caches are APCu and Redis. After installing and enabling your chosen memcache, verify that it is active by running [PHP version and information](#).

Note: If you run multiple web servers and enable a distributed cache in your `config.php` (`memcache.distributed`) or a file locking provider (`memcache.locking`) you need to make sure that they are referring to the very same memcache server and not to `localhost` or a unix socket.

5.4.1 APCu

APCu is a data cache, and it is available in most Linux distributions. On Red Hat/CentOS/Fedora systems install `php-pecl-apcu`. On Debian/Ubuntu/Mint systems install `php-apcu`.

After restarting your Web server, add this line to your `config.php` file:

```
'memcache.local' => '\OC\Memcache\APCu',
```

Refresh your Nextcloud admin page, and the cache warning should disappear.

Warning: APCu is disabled by default on CLI which could cause issues with nextcloud's cron jobs. Please make sure you set the `apc.enable_cli` to 1 on your `php.ini` config file or append `--define apc.enable_cli=1` to the cron job call.

5.4.2 Redis

Redis is an excellent modern memcache to use for distributed caching, and as a key-value store for [Transactional File Locking](#) because it guarantees that cached objects are available for as long as they are needed.

The Redis PHP module must be version 2.2.6+. If you are running a Linux distribution that does not package the supported versions of this module, or does not package Redis at all, see [Additional Redis installation help](#).

On Debian/Ubuntu/Mint install `redis-server` and `php-redis`. The installer will automatically launch `redis-server` and configure it to launch at startup.

On CentOS and Fedora install `redis` and `php-pecl-redis`. It will not start automatically, so you must use your service manager to start `redis`, and to launch it at boot as a daemon.

You can verify that the Redis daemon is running with `ps ax`:

```
ps ax | grep redis
22203 ? Ssl    0:00 /usr/bin/redis-server 127.0.0.1:6379
```

Restart your Web server, add the appropriate entries to your `config.php`, and refresh your Nextcloud admin page. This example `config.php` configuration uses Redis for the distributed server cache:

```
'memcache.distributed' => '\OC\Memcache\Redis',
'redis' => [
    'host' => 'redis-host.example.com',
    'port' => 6379,
],
```

For best performance, use Redis for file locking by adding this:

```
'memcache.locking' => '\OC\Memcache\Redis',
```

If you want to connect to Redis configured to listen on an Unix socket (which is recommended if Redis is running on the same system as Nextcloud) use this example `config.php` configuration:

```
'memcache.local' => '\OC\Memcache\APCu',
'memcache.distributed' => '\OC\Memcache\Redis',
'redis' => [
    'host'      => '/run/redis/redis-server.sock',
    'port'      => 0,
    'dbindex'   => 0,
    'password'  => 'secret',
    'timeout'   => 1.5,
],
```

Only “host” and “port” variables are required, the other ones are optional.

Update the redis configuration in `/etc/redis/redis.conf` accordingly: uncomment Unix socket options and ensure the “socket” and “port” settings match your Nextcloud configuration.

Be sure to set the right permissions on `redis.sock` so that your webserver can read and write to it. For this you typically have to add the webserver user to the redis group:

```
usermod -a -G redis www-data
```

You might need to restart apache for the changes to take effect:

```
systemctl restart apache2
```

Redis is very configurable; consult [the Redis documentation](#) to learn more.

Using the Redis session handler: If you are using Redis for locking and/or caching, you may also wish to use Redis for session management. Redis can be used for centralized session management across multiple Nextcloud application servers, unlike the standard *files* handler. If you use the Redis handler, though, you *MUST* ensure that session locking is enabled. As of this writing, the Redis session handler does *NOT* enable session locking by default, which can lead to session corruption in some Nextcloud apps that make heavy use of session writes such as Talk. In addition, even when session locking is enabled, if the application fails to acquire a lock, the Redis session handler does not currently return an error. Adding the following settings in your *php.ini* file will prevent session corruption when using Redis as your session handler:

```
redis.session.locking_enabled=1
redis.session.lock_retries=-1
redis.session.lock_wait_time=10000
```

More information on configuration of `phpredis` session handler can be found on the [PhpRedis GitHub page](#)

5.4.3 Memcached

Memcached is a reliable oldtimer for shared caching on distributed servers, and performs well with Nextcloud with one exception: it is not suitable to use with *Transactional File Locking* because it does not store locks, and data can disappear from the cache at any time (Redis is the best memcache for this).

Note: Be sure to install the **memcached** PHP module, and not memcache, as in the following examples. Nextcloud supports only the **memcached** PHP module.

Setting up Memcached is easy. On Debian/Ubuntu/Mint install memcached and php-memcached. The installer will automatically start memcached and configure it to launch at startup.

On Red Hat/CentOS/Fedora install memcached and php-pear-memcached. It will not start automatically, so you must use your service manager to start memcached, and to launch it at boot as a daemon.

You can verify that the Memcached daemon is running with `ps ax`:

```
ps ax | grep memcached
19563 ? Sl 0:02 /usr/bin/memcached -m 64 -p 11211 -u memcache -l
127.0.0.1
```

Restart your Web server, add the appropriate entries to your `config.php`, and refresh your Nextcloud admin page. This example uses APCu for the local cache, Memcached as the distributed memcache, and lists all the servers in the shared cache pool with their port numbers:

```
'memcache.local' => '\OC\Memcache\APCu',
'memcache.distributed' => '\OC\Memcache\Memcached',
'memcached_servers' => [
    [ 'server0.example.com', 11211 ],
    [ 'server1.example.com', 11211 ],
    [ 'server2.example.com', 11211 ],
],
```

5.4.4 Cache Directory location

The cache directory defaults to `data/$user/cache` where `$user` is the current user. You may use the `'cache_path'` directive in `config.php` (See *Configuration Parameters*) to select a different location.

5.4.5 Recommendations based on type of deployment

Small/Private home server

Only use APCu:

```
'memcache.local' => '\OC\Memcache\APCu',
```

Organizations with single-server and clustered setups

Use Redis for everything except local memcache:

```
'memcache.local' => '\OC\Memcache\APCu',  
'memcache.distributed' => '\OC\Memcache\Redis',  
'memcache.locking' => '\OC\Memcache\Redis',  
'redis' => [  
    'host' => 'redis-host.example.com',  
    'port' => 6379,  
],
```

Additional notes for Redis vs. APCu on memory caching

APCu is faster at local caching than Redis. If you have enough memory, use APCu for Memory Caching and Redis for File Locking. If you are low on memory, use Redis for both.

5.4.6 Additional Redis installation help

If your version of Mint or Ubuntu does not package the required version of `php-redis`, then try [this Redis guide on Tech and Me](#) for a complete Redis installation on Ubuntu 14.04 using PECL. These instructions are adaptable for any distro that does not package the supported version, or that does not package Redis at all, such as SUSE Linux Enterprise Server and Red Hat Enterprise Linux.

For PHP 7.0 and PHP 7.1 use Redis PHP module 3.1.x or later.

See <https://pecl.php.net/package/redis>

On Debian/Mint/Ubuntu, use `apt-cache` to see the available `php-redis` version, or the version of your installed package:

```
apt-cache policy php-redis
```

On CentOS and Fedora, the `yum` command shows available and installed version information:

```
yum search php-pecl-redis
```

5.5 Background jobs

A system like Nextcloud sometimes requires tasks to be done on a regular basis without the need for user interaction or hindering Nextcloud performance. For that purpose, as a system administrator, you can define background jobs (for example, database clean-ups) which are executed without any need for user interaction.

These jobs are typically referred to as *cron jobs*. Cron jobs are commands or shell-based scripts that are scheduled to run periodically at fixed times, dates, or intervals. `cron.php` is a Nextcloud internal process that runs such background jobs on demand.

Nextcloud apps register actions with `cron.php` automatically to take care of typical housekeeping operations, such as garbage collecting of temporary files or checking for newly updated files using `filescan()` for externally mounted file systems.

5.5.1 Parameters

In the admin settings menu you can configure how cron-jobs should be executed. You can choose between the following options:

- AJAX
- Webcron
- Cron

5.5.2 Cron jobs

You can schedule cron jobs in three ways – using AJAX, Webcron, or cron. The default method is to use AJAX. However, the recommended method is to use cron. The following sections describe the differences between each method.

AJAX

The AJAX scheduling method is the default option. Unfortunately, however, it is also the least reliable. Each time a user visits the Nextcloud page, a single background job is executed. The advantage of this mechanism is that it does not require access to the system nor registration with a third party service. The disadvantage of this mechanism, when compared to the Webcron service, is that it requires regular visits to the page for it to be triggered.

Note: Especially when using the Activity App or external storages, where new files are added, updated or deleted one of the two methods below should be preferred.

Webcron

By registering your Nextcloud `cron.php` script address at an external webcron service (for example, [easyCron](#)), you ensure that background jobs are executed regularly. To use this type of service with your server, you must be able to access your server using the Internet. For example:

URL to call: `http[s]://<domain-of-your-server>/nextcloud/cron.php`

Cron

Using the operating system cron feature is the preferred method for executing regular tasks. This method enables the execution of scheduled jobs without the inherent limitations the Web server might have.

To run a cron job on a *nix system, every 5 minutes, under the default Web server user (often, `www-data` or `wwwrun`), you must set up the following cron job to call the **`cron.php`** script:

```
# crontab -u www-data -e
```

And append this line:

```
*/5 * * * * php -f /var/www/nextcloud/cron.php
```

You can verify if the cron job has been added and scheduled by executing:

```
# crontab -u www-data -l
```

Which returns:

```
[snip]
*/5 * * * * php -f /var/www/nextcloud/cron.php
```

Note: You have to replace the path `/var/www/nextcloud/cron.php` with the path to your current Nextcloud installation.

Note: On some systems it might be required to call **php-cli** instead of **php**.

Note: For some configurations, it might be necessary to append `--define apc.enable_cli=1` to the cron command. Please refer to [Memory caching](#) (section APCu).

Note: Please refer to the crontab man page for the exact command syntax.

systemd

If systemd is installed on the system, a systemd timer could be an alternative to a cronjob.

This approach requires two files: **nextcloudcron.service** and **nextcloudcron.timer**. Create these two files in `/etc/systemd/system/`.

nextcloudcron.service should look like this:

```
[Unit]
Description=Nextcloud cron.php job

[Service]
User=www-data
ExecStart=/usr/bin/php -f /var/www/nextcloud/cron.php
KillMode=process
```

Replace the user `www-data` with the user of your http server and `/var/www/nextcloud/cron.php` with the location of **cron.php** in your nextcloud directory.

The `KillMode=process` setting is necessary for external programs that are started by the cron job to keep running after the cron job has finished.

Note that the **.service** unit file does not need an `[Install]` section. Please check your setup because we recommended it in earlier versions of this admin manual.

nextcloudcron.timer should look like this:

```
[Unit]
Description=Run Nextcloud cron.php every 5 minutes
```

(continues on next page)

(continued from previous page)

```
[Timer]
OnBootSec=5min
OnUnitActiveSec=5min
Unit=nextcloudcron.service

[Install]
WantedBy=timers.target
```

The important parts in the timer-unit are `OnBootSec` and `OnUnitActiveSec`. `OnBootSec` will start the timer 5 minutes after boot, otherwise you would have to start it manually after every boot. `OnUnitActiveSec` will set a 5 minute timer after the service-unit was last activated.

Now all that is left is to start and enable the timer by running this command:

```
systemctl enable --now nextcloudcron.timer
```

When the option `--now` is used with `enable`, the respective unit will also be started.

Note: Selecting the option `Cron` in the admin menu for background jobs is not mandatory, because once `cron.php` is executed from the command line or cron service it will set it automatically to `Cron`.

5.6 Configuration Parameters

Nextcloud uses the `config/config.php` file to control server operations. `config/config.sample.php` lists all the configurable parameters within Nextcloud, along with example or default values. This document provides a more detailed reference. Most options are configurable on your Admin page, so it is usually not necessary to edit `config/config.php`.

Note: The installer creates a configuration containing the essential parameters. Only manually add configuration parameters to `config/config.php` if you need to use a special value for a parameter. **Do not copy everything from `config/config.sample.php`. Only enter the parameters you wish to modify!**

5.6.1 Multiple config.php file

Nextcloud supports loading configuration parameters from multiple files. You can add arbitrary files ending with `.config.php` in the `config/` directory, for example you could place your email server configuration in `email.config.php`. This allows you to easily create and manage custom configurations, or to divide a large complex configuration file into a set of smaller files. These custom files are not overwritten by Nextcloud, and the values in these files take precedence over `config.php`.

5.6.2 Default Parameters

These parameters are configured by the Nextcloud installer, and are required for your Nextcloud server to operate.

```
'instanceid' => '',
```

This is a unique identifier for your Nextcloud installation, created automatically by the installer. This example is for documentation only, and you should never use it because it will not work. A valid `instanceid` is created when you install Nextcloud.

```
'instanceid' => 'd3c944a9a',
```

```
'passwordsalt' => '',
```

The salt used to hash all passwords, auto-generated by the Nextcloud installer. (There are also per-user salts.) If you lose this salt you lose all your passwords. This example is for documentation only, and you should never use it.

```
'trusted_domains' =>
[
    'demo.example.org',
    'otherdomain.example.org',
    '10.111.112.113',
    '[2001:db8::1]'
],
```

Your list of trusted domains that users can log into. Specifying trusted domains prevents host header poisoning. Do not remove this, as it performs necessary security checks.

You can specify:

- the exact hostname of your host or virtual host, e.g. `demo.example.org`.
- the exact hostname with permitted port, e.g. `demo.example.org:443`. This disallows all other ports on this host
- use `*` as a wildcard, e.g. `ubos-raspberry-pi*.local` will allow `ubos-raspberry-pi.local` and `ubos-raspberry-pi-2.local`
- the IP address with or without permitted port, e.g. `[2001:db8::1]:8080` Using TLS certificates where common-Name=<IP address> is deprecated

```
'datadirectory' => '/var/www/nextcloud/data',
```

Where user files are stored. The SQLite database is also stored here, when you use SQLite.

Default to `data/` in the Nextcloud directory.

```
'version' => '',
```

The current version number of your Nextcloud installation. This is set up during installation and update, so you shouldn't need to change it.

```
'dbtype' => 'sqlite3',
```

Identifies the database used with this installation. See also config option `supportedDatabases`

Available:

- `sqlite3` (SQLite3)
- `mysql` (MySQL/MariaDB)

- pgsql (PostgreSQL)

Defaults to `sqlite3`

```
'dbhost' => '',
```

Your host server name, for example `localhost`, `hostname`, `hostname.example.com`, or the IP address. To specify a port use `hostname:####`; to specify a Unix socket use `localhost:/path/to/socket`.

```
'dbname' => 'nextcloud',
```

The name of the Nextcloud database, which is set during installation. You should not need to change this.

```
'dbuser' => '',
```

The user that Nextcloud uses to write to the database. This must be unique across Nextcloud instances using the same SQL database. This is set up during installation, so you shouldn't need to change it.

```
'dbpassword' => '',
```

The password for the database user. This is set up during installation, so you shouldn't need to change it.

```
'dbtableprefix' => '',
```

Prefix for the Nextcloud tables in the database.

Default to `oc_`

```
'installed' => false,
```

Indicates whether the Nextcloud instance was installed successfully; `true` indicates a successful installation, and `false` indicates an unsuccessful installation.

Defaults to `false`

5.6.3 Default config.php Examples

When you use SQLite as your Nextcloud database, your `config.php` looks like this after installation. The SQLite database is stored in your Nextcloud `data/` directory. SQLite is a simple, lightweight embedded database that is good for testing and for simple installations, but for production Nextcloud systems you should use MySQL, MariaDB, or PostgreSQL.

```
<?php
$CONFIG = array (
    'instanceid' => 'occ6f7365735',
    'passwordsalt' => '2c5778476346786306303',
    'trusted_domains' =>
    array (
        0 => 'localhost',
        1 => 'studio',
    ),
    'datadirectory' => '/var/www/nextcloud/data',
    'dbtype' => 'sqlite3',
    'version' => '7.0.2.1',
    'installed' => true,
);
```

This example is from a new Nextcloud installation using MariaDB:

```
<?php
$CONFIG = array (
  'instanceid' => 'oc8c0fd71e03',
  'passwordsalt' => '515a13302a6b3950a9d0fdb970191a',
  'trusted_domains' =>
  array (
    0 => 'localhost',
    1 => 'studio',
    2 => '192.168.10.155'
  ),
  'datadirectory' => '/var/www/nextcloud/data',
  'dbtype' => 'mysql',
  'version' => '7.0.2.1',
  'dbname' => 'nextcloud',
  'dbhost' => 'localhost',
  'dbtableprefix' => 'oc_',
  'dbuser' => 'oc_carla',
  'dbpassword' => '67336bcd7630dd80b2b81a413d07',
  'installed' => true,
);
```

5.6.4 User Experience

These optional parameters control some aspects of the user interface. Default values, where present, are shown.

```
'default_language' => 'en',
```

This sets the default language on your Nextcloud server, using ISO_639-1 language codes such as `en` for English, `de` for German, and `fr` for French. It overrides automatic language detection on public pages like login or shared items. User's language preferences configured under “personal -> language” override this setting after they have logged in. Nextcloud has two distinguished language codes for German, `de` and `de_DE`. `de` is used for informal German and `de_DE` for formal German. By setting this value to `de_DE` you can enforce the formal version of German unless the user has chosen something different explicitly.

Defaults to `en`

```
'force_language' => 'en',
```

With this setting a language can be forced for all users. If a language is forced, the users are also unable to change their language in the personal settings. If users shall be unable to change their language, but users have different languages, this value can be set to `true` instead of a language code.

Defaults to `false`

```
'default_locale' => 'en_US',
```

This sets the default locale on your Nextcloud server, using ISO_639 language codes such as `en` for English, `de` for German, and `fr` for French, and ISO-3166 country codes such as `GB`, `US`, `CA`, as defined in RFC 5646. It overrides automatic locale detection on public pages like login or shared items. User's locale preferences configured under “personal -> locale” override this setting after they have logged in.

Defaults to `en`

```
'default_phone_region' => 'GB',
```

This sets the default region for phone numbers on your Nextcloud server, using ISO 3166-1 country codes such as DE for Germany, FR for France, ... It is required to allow inserting phone numbers in the user profiles starting without the country code (e.g. +49 for Germany).

No default value!

```
'force_locale' => 'en_US',
```

With this setting a locale can be forced for all users. If a locale is forced, the users are also unable to change their locale in the personal settings. If users shall be unable to change their locale, but users have different languages, this value can be set to `true` instead of a locale code.

Defaults to `false`

```
'defaultapp' => 'dashboard,files',
```

Set the default app to open on login. Use the app names as they appear in the URL after clicking them in the Apps menu, such as documents, calendar, and gallery. You can use a comma-separated list of app names, so if the first app is not enabled for a user then Nextcloud will try the second one, and so on. If no enabled apps are found it defaults to the dashboard app.

Defaults to `dashboard,files`

```
'knowledgebaseenabled' => true,
```

`true` enables the Help menu item in the user menu (top right of the Nextcloud Web interface). `false` removes the Help item.

```
'allow_user_to_change_display_name' => true,
```

`true` allows users to change their display names (on their Personal pages), and `false` prevents them from changing their display names.

```
'remember_login_cookie_lifetime' => 60*60*24*15,
```

Lifetime of the remember login cookie. This should be larger than the `session_lifetime`. If it is set to 0 remember me is disabled.

Defaults to `60*60*24*15` seconds (15 days)

```
'session_lifetime' => 60 * 60 * 24,
```

The lifetime of a session after inactivity.

Defaults to `60*60*24` seconds (24 hours)

```
'session_keepalive' => true,
```

Enable or disable session keep-alive when a user is logged in to the Web UI.

Enabling this sends a “heartbeat” to the server to keep it from timing out.

Defaults to `true`

```
'auto_logout' => false,
```

Enable or disable the automatic logout after session_lifetime, even if session keepalive is enabled. This will make sure that an inactive browser will be logged out even if requests to the server might extend the session lifetime.

Defaults to `false`

```
'token_auth_enforced' => false,
```

Enforce token authentication for clients, which blocks requests using the user password for enhanced security. Users need to generate tokens in personal settings which can be used as passwords on their clients.

Defaults to `false`

```
'token_auth_activity_update' => 60,
```

The interval at which token activity should be updated.

Increasing this value means that the last activity on the security page gets more outdated.

Tokens are still checked every 5 minutes for validity max value: 300

Defaults to `300`

```
'auth.bruteforce.protection.enabled' => true,
```

Whether the bruteforce protection shipped with Nextcloud should be enabled or not.

Disabling this is discouraged for security reasons.

Defaults to `true`

```
'auth.authtoken.v1.disabled' => false,
```

Whether the authtoken v1 provider should be skipped

The v1 provider is deprecated and removed in Nextcloud 24 onwards. It can be disabled already when the instance was installed after Nextcloud 14.

Defaults to `false`

```
'auth.webauthn.enabled' => true,
```

By default WebAuthn is available but it can be explicitly disabled by admins

```
'skeletondirectory' => '/path/to/nextcloud/core/skeleton',
```

The directory where the skeleton files are located. These files will be copied to the data directory of new users. Leave empty to not copy any skeleton files.

{lang} can be used as a placeholder for the language of the user. If the directory does not exist, it falls back to non dialect (from de_DE to de). If that does not exist either, it falls back to default

Defaults to `core/skeleton` in the Nextcloud directory.

```
'templatedirectory' => '/path/to/nextcloud/templates',
```

The directory where the template files are located. These files will be copied to the template directory of new users. Leave empty to not copy any template files.

{lang} can be used as a placeholder for the language of the user. If the directory does not exist, it falls back to non dialect (from de_DE to de). If that does not exist either, it falls back to default

If this is not set creating a template directory will only happen if no custom `skeletondirectory` is defined, otherwise the shipped templates will be used to create a template directory for the user.

```
'lost_password_link' => 'https://example.org/link/to/password/reset',
```

If your user backend does not allow password resets (e.g. when it's a read-only user backend like LDAP), you can specify a custom link, where the user is redirected to, when clicking the “reset password” link after a failed login-attempt.

In case you do not want to provide any link, replace the url with ‘disabled’

5.6.5 Mail Parameters

These configure the email settings for Nextcloud notifications and password resets.

```
'mail_domain' => 'example.com',
```

The return address that you want to appear on emails sent by the Nextcloud server, for example `nc-admin@example.com`, substituting your own domain, of course.

```
'mail_from_address' => 'nextcloud',
```

FROM address that overrides the built-in `sharing-noreply` and `lostpassword-noreply` FROM addresses.

Defaults to different from addresses depending on the feature.

```
'mail_smtpdebug' => false,
```

Enable SMTP class debugging.

Defaults to `false`

```
'mail_smtpmode' => 'smtp',
```

Which mode to use for sending mail: `sendmail`, `smtp` or `qmail`.

If you are using local or remote SMTP, set this to `smtp`.

For the `sendmail` option you need an installed and working email system on the server, with `/usr/sbin/sendmail` installed on your Unix system.

For `qmail` the binary is `/var/qmail/bin/sendmail`, and it must be installed on your Unix system.

Defaults to `smtp`

```
'mail_smtphost' => '127.0.0.1',
```

This depends on `mail_smtpmode`. Specify the IP address of your mail server host. This may contain multiple hosts separated by a semi-colon. If you need to specify the port number append it to the IP address separated by a colon, like this: `127.0.0.1:24`.

Defaults to `127.0.0.1`

```
'mail_smtpport' => 25,
```

This depends on `mail_smtpmode`. Specify the port for sending mail.

Defaults to `25`

```
'mail_smtptimeout' => 10,
```

This depends on `mail_smtpmode`. This sets the SMTP server timeout, in seconds. You may need to increase this if you are running an anti-malware or spam scanner.

Defaults to 10 seconds

```
'mail_smtpsecure' => '',
```

This depends on `mail_smtpmode`. Specify when you are using `ssl` for SSL/TLS or `tls` for STARTTLS, or leave empty for no encryption.

Defaults to '' (empty string)

```
'mail_smtpauth' => false,
```

This depends on `mail_smtpmode`. Change this to `true` if your mail server requires authentication.

Defaults to `false`

```
'mail_smtpauthtype' => 'LOGIN',
```

This depends on `mail_smtpmode`. If SMTP authentication is required, choose the authentication type as `LOGIN` or `PLAIN`.

Defaults to `LOGIN`

```
'mail_smtpname' => '',
```

This depends on `mail_smtpauth`. Specify the username for authenticating to the SMTP server.

Defaults to '' (empty string)

```
'mail_smtppassword' => '',
```

This depends on `mail_smtpauth`. Specify the password for authenticating to the SMTP server.

Default to '' (empty string)

```
'mail_template_class' => '\OC\Mail\EMailTemplate',
```

Replaces the default mail template layout. This can be utilized if the options to modify the mail texts with the theming app is not enough.

The class must extend `\OC\Mail\EMailTemplate`

```
'mail_send_plaintext_only' => false,
```

Email will be send by default with an HTML and a plain text body. This option allows to only send plain text emails.

```
'mail_smtpstreamoptions' => [],
```

This depends on `mail_smtpmode`. Array of additional streams options that will be passed to underlying Swift mailer implementation.

Defaults to an empty array.

```
'mail_sendmailmode' => 'smtp',
```

Which mode is used for sendmail/qmail: `smtp` or `pipe`.

For `smtp` the sendmail binary is started with the parameter `-bs`:

- Use the SMTP protocol on standard input and output.

For `pipe` the binary is started with the parameters `-t`:

- Read message from STDIN and extract recipients.

Defaults to `smtp`

5.6.6 Proxy Configurations

```
'overwritehost' => '',
```

The automatic hostname detection of Nextcloud can fail in certain reverse proxy and CLI/cron situations. This option allows you to manually override the automatic detection; for example `www.example.com`, or specify the port `www.example.com:8080`.

```
'overwriteprotocol' => '',
```

When generating URLs, Nextcloud attempts to detect whether the server is accessed via `https` or `http`. However, if Nextcloud is behind a proxy and the proxy handles the `https` calls, Nextcloud would not know that `ssl` is in use, which would result in incorrect URLs being generated.

Valid values are `http` and `https`.

```
'overwritewebroot' => '',
```

Nextcloud attempts to detect the webroot for generating URLs automatically.

For example, if `www.example.com/nextcloud` is the URL pointing to the Nextcloud instance, the webroot is `/nextcloud`. When proxies are in use, it may be difficult for Nextcloud to detect this parameter, resulting in invalid URLs.

```
'overwritecondaddr' => '',
```

This option allows you to define a manual override condition as a regular expression for the remote IP address. For example, defining a range of IP addresses starting with `10.0.0.` and ending with 1 to 3: `^10\.\0\.\0\.[1-3]$`

Defaults to `''` (empty string)

```
'overwrite.cli.url' => '',
```

Use this configuration parameter to specify the base URL for any URLs which are generated within Nextcloud using any kind of command line tools (cron or occ). The value should contain the full base URL: `https://www.example.com/nextcloud`

Defaults to `''` (empty string)

```
'htaccess.RewriteBase' => '/',
```

To have clean URLs without `/index.php` this parameter needs to be configured.

This parameter will be written as “RewriteBase” on update and installation of Nextcloud to your `.htaccess` file. While this value is often simply the URL path of the Nextcloud installation it cannot be set automatically properly in every scenario and needs thus some manual configuration.

In a standard Apache setup this usually equals the folder that Nextcloud is accessible at. So if Nextcloud is accessible via “<https://mycloud.org/nextcloud>” the correct value would most likely be “/nextcloud”. If Nextcloud is running under “<https://mycloud.org/>” then it would be “/”.

Note that the above rule is not valid in every case, as there are some rare setup cases where this may not apply. However, to avoid any update problems this configuration value is explicitly opt-in.

After setting this value run *occ maintenance:update:htaccess*. Now, when the following conditions are met Nextcloud URLs won’t contain *index.php*:

- *mod_rewrite* is installed
- *mod_env* is installed

Defaults to '' (empty string)

```
'htaccess.IgnoreFrontController' => false,
```

For server setups, that don’t have *mod_env* enabled or restricted (e.g. suEXEC) this parameter has to be set to true and will assume *mod_rewrite*.

Please check, if *mod_rewrite* is active and functional before setting this parameter and you updated your .htaccess with *occ maintenance:update:htaccess*. Otherwise your nextcloud installation might not be reachable anymore. For example, try accessing resources by leaving out *index.php* in the URL.

```
'proxy' => '',
```

The URL of your proxy server, for example `proxy.example.com:8081`.

Note: Guzzle (the http library used by Nextcloud) is reading the environment variables HTTP_PROXY (only for cli request), HTTPS_PROXY, and NO_PROXY by default.

If you configure proxy with Nextcloud any default configuration by Guzzle is overwritten. Make sure to set `proxyexclude` accordingly if necessary.

Defaults to '' (empty string)

```
'proxyuserpwd' => '',
```

The optional authentication for the proxy to use to connect to the internet.

The format is: `username:password`.

Defaults to '' (empty string)

```
'proxyexclude' => [],
```

List of host names that should not be proxied to.

For example: `['.mit.edu', 'foo.com']`.

Hint: Use something like `explode(',', getenv('NO_PROXY'))` to sync this value with the global NO_PROXY option.

Defaults to empty array.

```
'allow_local_remote_servers' => true,
```

Allow remote servers with local addresses e.g. in federated shares, webcal services and more

Defaults to false

5.6.7 Deleted Items (trash bin)

These parameters control the Deleted files app.

```
'trashbin_retention_obligation' => 'auto',
```

If the trash bin app is enabled (default), this setting defines the policy for when files and folders in the trash bin will be permanently deleted.

The app allows for two settings, a minimum time for trash bin retention, and a maximum time for trash bin retention. Minimum time is the number of days a file will be kept, after which it may be deleted. Maximum time is the number of days at which it is guaranteed to be deleted. Both minimum and maximum times can be set together to explicitly define file and folder deletion. For migration purposes, this setting is installed initially set to “auto”, which is equivalent to the default setting in Nextcloud.

Available values:

- **auto** default setting. keeps files and folders in the trash bin for 30 days and automatically deletes anytime after that if space is needed (note: files may not be deleted if space is not needed).
- **D, auto** keeps files and folders in the trash bin for D+ days, delete anytime if space needed (note: files may not be deleted if space is not needed)
- **auto, D** delete all files in the trash bin that are older than D days automatically, delete other files anytime if space needed
- **D1, D2** keep files and folders in the trash bin for at least D1 days and delete when exceeds D2 days (note: files will not be deleted automatically if space is needed)
- **disabled** trash bin auto clean disabled, files and folders will be kept forever

Defaults to auto

5.6.8 File versions

These parameters control the Versions app.

```
'versions_retention_obligation' => 'auto',
```

If the versions app is enabled (default), this setting defines the policy for when versions will be permanently deleted.

The app allows for two settings, a minimum time for version retention, and a maximum time for version retention. Minimum time is the number of days a version will be kept, after which it may be deleted. Maximum time is the number of days at which it is guaranteed to be deleted. Both minimum and maximum times can be set together to explicitly define version deletion. For migration purposes, this setting is installed initially set to “auto”, which is equivalent to the default setting in Nextcloud.

Available values:

- **auto** default setting. Automatically expire versions according to expire rules. Please refer to [Controlling file versions and aging](#) for more information.
- **D, auto** keep versions at least for D days, apply expire rules to all versions that are older than D days
- **auto, D** delete all versions that are older than D days automatically, delete other versions according to expire rules
- **D1, D2** keep versions for at least D1 days and delete when exceeds D2 days
- **disabled** versions auto clean disabled, versions will be kept forever

Defaults to auto

5.6.9 Nextcloud Verifications

Nextcloud performs several verification checks. There are two options, `true` and `false`.

```
'appcodechecker' => true,
```

Checks an app before install whether it uses private APIs instead of the proper public APIs. If this is set to `true` it will only allow to install or enable apps that pass this check.

Defaults to `false`

```
'updatechecker' => true,
```

Check if Nextcloud is up-to-date and shows a notification if a new version is available.

Defaults to `true`

```
'updater.server.url' => 'https://updates.nextcloud.com/updater_server/',
```

URL that Nextcloud should use to look for updates

Defaults to `https://updates.nextcloud.com/updater_server/`

```
'updater.release.channel' => 'stable',
```

The channel that Nextcloud should use to look for updates

Supported values:

- `daily`
- `beta`
- `stable`

```
'has_internet_connection' => true,
```

Is Nextcloud connected to the Internet or running in a closed network?

Defaults to `true`

```
'connectivity_check_domains' => [  
    'www.nextcloud.com',  
    'www.startpage.com',  
    'www.eff.org',  
    'www.edri.org'  
],
```

Which domains to request to determine the availability of an Internet connection. If none of these hosts are reachable, the administration panel will show a warning. Set to an empty list to not do any such checks (warning will still be shown).

Defaults to the following domains:

- `www.nextcloud.com`
- `www.startpage.com`
- `www.eff.org`
- `www.edri.org`

```
'check_for_working_wellknown_setup' => true,
```

Allows Nextcloud to verify a working .well-known URL redirects. This is done by attempting to make a request from JS to <https://your-domain.com/.well-known/caldav/>

Defaults to `true`

```
'check_for_working_htaccess' => true,
```

This is a crucial security check on Apache servers that should always be set to `true`. This verifies that the `.htaccess` file is writable and works.

If it is not, then any options controlled by `.htaccess`, such as large file uploads, will not work. It also runs checks on the `data/` directory, which verifies that it can't be accessed directly through the Web server.

Defaults to `true`

```
'check_data_directory_permissions' => true,
```

In rare setups (e.g. on Openshift or docker on windows) the permissions check might block the installation while the underlying system offers no means to “correct” the permissions. In this case, set the value to `false`.

In regular cases, if issues with permissions are encountered they should be adjusted accordingly. Changing the flag is discouraged.

Defaults to `true`

```
'config_is_read_only' => false,
```

In certain environments it is desired to have a read-only configuration file.

When this switch is set to `true` Nextcloud will not verify whether the configuration is writable. However, it will not be possible to configure all options via the Web interface. Furthermore, when updating Nextcloud it is required to make the configuration file writable again for the update process.

Defaults to `false`

5.6.10 Logging

```
'log_type' => 'file',
```

This parameter determines where the Nextcloud logs are sent.

`file`: the logs are written to file `nextcloud.log` in the default Nextcloud data directory. The log file can be changed with parameter `logfile`. `syslog`: the logs are sent to the system log. This requires a syslog daemon to be active. `errorlog`: the logs are sent to the PHP `error_log` function. `systemd`: the logs are sent to the Systemd journal. This requires a system that runs Systemd and the Systemd journal. The PHP extension `systemd` must be installed and active.

Defaults to `file`

```
'logfile' => '/var/log/nextcloud.log',
```

Name of the file to which the Nextcloud logs are written if parameter `log_type` is set to `file`.

Defaults to `[datadirectory]/nextcloud.log`

```
'logfilemode' => 0640,
```

Log file mode for the Nextcloud login type in octal notation.

Defaults to 0640 (writeable by user, readable by group).

```
'loglevel' => 2,
```

Loglevel to start logging at. Valid values are: 0 = Debug, 1 = Info, 2 = Warning, 3 = Error, and 4 = Fatal. The default value is Warning.

Defaults to 2

```
'syslog_tag' => 'Nextcloud',
```

If you maintain different instances and aggregate the logs, you may want to distinguish between them. `syslog_tag` can be set per instance with a unique id. Only available if `log_type` is set to `syslog` or `systemd`.

The default value is `Nextcloud`.

```
'log.condition' => [  
    'shared_secret' => '57b58edb6637fe3059b3595cf9c41b9',  
    'users' => ['sample-user'],  
    'apps' => ['files'],  
],
```

Log condition for log level increase based on conditions. Once one of these conditions is met, the required log level is set to debug. This allows to debug specific requests, users or apps

Supported conditions:

- **shared_secret:** if a request parameter with the name `log_secret` is set to this value the condition is met
- **users:** if the current request is done by one of the specified users, this condition is met
- **apps:** if the log message is invoked by one of the specified apps, this condition is met

Defaults to an empty array.

```
'logdateformat' => 'F d, Y H:i:s',
```

This uses PHP date formatting; see <https://www.php.net/manual/en/function.date.php>

Defaults to ISO 8601 2005-08-15T15:52:01+00:00 - see `DateTime::ATOM` (<https://www.php.net/manual/en/class.datetime.php#datetime.constants.atom>)

```
'logtimezone' => 'Europe/Berlin',
```

The timezone for logfiles. You may change this; see <https://www.php.net/manual/en/timezones.php>

Defaults to UTC

```
'log_query' => false,
```

Append all database queries and parameters to the log file. Use this only for debugging, as your logfile will become huge.

```
'log_rotate_size' => 100 * 1024 * 1024,
```

Enables log rotation and limits the total size of logfiles. Set it to 0 for no rotation. Specify a size in bytes, for example 104857600 (100 megabytes = 100 * 1024 * 1024 bytes). A new logfile is created with a new name when the old logfile reaches your limit. If a rotated log file is already present, it will be overwritten.

Defaults to 100 MB

5.6.11 Alternate Code Locations

Some of the Nextcloud code may be stored in alternate locations.

```
'customclient_desktop' =>
    'https://nextcloud.com/install/#install-clients',
'customclient_android' =>
    'https://play.google.com/store/apps/details?id=com.nextcloud.client',
'customclient_ios' =>
    'https://itunes.apple.com/us/app/nextcloud/id1125420102?mt=8',
'customclient_ios_appid' =>
    '1125420102',
```

This section is for configuring the download links for Nextcloud clients, as seen in the first-run wizard and on Personal pages.

Defaults to:

- Desktop client: <https://nextcloud.com/install/#install-clients>
- Android client: <https://play.google.com/store/apps/details?id=com.nextcloud.client>
- iOS client: <https://itunes.apple.com/us/app/nextcloud/id1125420102?mt=8>
- iOS client app id: 1125420102

5.6.12 Apps

Options for the Apps folder, Apps store, and App code checker.

```
'appstoreenabled' => true,
```

When enabled, admins may install apps from the Nextcloud app store.

Defaults to true

```
'appstoreurl' => 'https://apps.nextcloud.com/api/v1',
```

Enables the installation of apps from a self hosted apps store.

Requires that at least one of the configured apps directories is writeable.

Defaults to <https://apps.nextcloud.com/api/v1>

```
'apps_paths' => [
    [
        'path' => '/var/www/nextcloud/apps',
        'url' => '/apps',
        'writable' => true,
    ],
],
```

Use the `apps_paths` parameter to set the location of the Apps directory, which should be scanned for available apps, and where user-specific apps should be installed from the Apps store. The `path` defines the absolute file system path to the app folder. The key `url` defines the HTTP Web path to that folder, starting from the Nextcloud webroot. The key `writable` indicates if a Web server can write files to that folder.

```
'appcodechecker' => true,
```

Checks an app before install whether it uses private APIs instead of the proper public APIs. If this is set to true it will only allow to install or enable apps that pass this check.

Defaults to `false`

5.6.13 Previews

Nextcloud supports previews of image files, the covers of MP3 files, and text files. These options control enabling and disabling previews, and thumbnail size.

```
'enable_previews' => true,
```

By default, Nextcloud can generate previews for the following filetypes:

- Image files
- Covers of MP3 files
- Text documents

Valid values are `true`, to enable previews, or `false`, to disable previews

Defaults to `true`

```
'preview_max_x' => 4096,
```

The maximum width, in pixels, of a preview. A value of `null` means there is no limit.

Defaults to `4096`

```
'preview_max_y' => 4096,
```

The maximum height, in pixels, of a preview. A value of `null` means there is no limit.

Defaults to `4096`

```
'preview_max_filesize_image' => 50,
```

max file size for generating image previews with `imagegd` (default behavior) If the image is bigger, it'll try other preview generators, but will most likely show the default mimetype icon. Set to `-1` for no limit.

Defaults to `50` megabytes

```
'preview_max_memory' => 128,
```

max memory for generating image previews with `imagegd` (default behavior) Reads the image dimensions from the header and assumes 32 bits per pixel.

If creating the image would allocate more memory, preview generation will be disabled and the default mimetype icon is shown. Set to `-1` for no limit.

Defaults to `128` megabytes

```
'preview_libreoffice_path' => '/usr/bin/libreoffice',
```

custom path for LibreOffice/OpenOffice binary

Defaults to '' (empty string)

```
'preview_office_cli_parameters' =>
    ' --headless --nologo --nofirststartwizard --invisible --norestore '.
    '--convert-to png --outdir ',
```

Use this if LibreOffice/OpenOffice requires additional arguments.

Defaults to '' (empty string)

```
'enabledPreviewProviders' => [
    'OC\Preview\PNG',
    'OC\Preview\JPEG',
    'OC\Preview\GIF',
    'OC\Preview\BMP',
    'OC\Preview\XBitmap',
    'OC\Preview\MP3',
    'OC\Preview\TXT',
    'OC\Preview\Markdown',
    'OC\Preview\OpenDocument',
    'OC\Preview\Krita',
],
```

Only register providers that have been explicitly enabled

The following providers are disabled by default due to performance or privacy concerns:

- OC\Preview\Illustrator
- OC\Preview\HEIC
- OC\Preview\Movie
- OC\Preview\MSOffice2003
- OC\Preview\MSOffice2007
- OC\Preview\MSOfficeDoc
- OC\Preview\PDF
- OC\Preview\Photoshop
- OC\Preview\Postscript
- OC\Preview\StarOffice
- OC\Preview\SVG
- OC\Preview\TIFF
- OC\Preview\Font

Defaults to the following providers:

- OC\Preview\BMP
- OC\Preview\GIF
- OC\Preview\JPEG

- OC\Preview\MarkDown
- OC\Preview\MP3
- OC\Preview\PNG
- OC\Preview\TXT
- OC\Preview\XBitmap
- OC\Preview\OpenDocument
- OC\Preview\Krita

5.6.14 LDAP

Global settings used by LDAP User and Group Backend

```
'ldapUserCleanupInterval' => 51,
```

defines the interval in minutes for the background job that checks user existence and marks them as ready to be cleaned up. The number is always minutes. Setting it to 0 disables the feature.

See command line (occ) methods `ldap:show-remnants` and `user:delete`

Defaults to 51 minutes

```
'sort_groups_by_name' => false,
```

Sort groups in the user settings by name instead of the user count

By enabling this the user count beside the group name is disabled as well.

5.6.15 Comments

Global settings for the Comments infrastructure

```
'comments.managerFactory' => '\OC\Comments\ManagerFactory',
```

Replaces the default Comments Manager Factory. This can be utilized if an own or 3rdParty CommentsManager should be used that – for instance – uses the filesystem instead of the database to keep the comments.

Defaults to `\OC\Comments\ManagerFactory`

```
'systemtags.managerFactory' => '\OC\SystemTag\ManagerFactory',
```

Replaces the default System Tags Manager Factory. This can be utilized if an own or 3rdParty SystemTagsManager should be used that – for instance – uses the filesystem instead of the database to keep the tags.

Defaults to `\OC\SystemTag\ManagerFactory`

5.6.16 Maintenance

These options are for halting user activity when you are performing server maintenance.

```
'maintenance' => false,
```

Enable maintenance mode to disable Nextcloud

If you want to prevent users from logging in to Nextcloud before you start doing some maintenance work, you need to set the value of the maintenance parameter to true. Please keep in mind that users who are already logged-in are kicked out of Nextcloud instantly.

Defaults to false

5.6.17 SSL

```
'openssl' => [
    'config' => '/absolute/location/of/openssl.cnf',
],
```

Extra SSL options to be used for configuration.

Defaults to an empty array.

5.6.18 Memory caching backend configuration

Available cache backends:

- \OC\Memcache\APCu APC user backend
- \OC\Memcache\ArrayCache In-memory array-based backend (not recommended)
- \OC\Memcache\Memcached Memcached backend
- \OC\Memcache\Redis Redis backend

Advice on choosing between the various backends:

- APCu should be easiest to install. Almost all distributions have packages. Use this for single user environment for all caches.
- Use Redis or Memcached for distributed environments. For the local cache (you can configure two) take APCu.

```
'memcache.local' => '\OC\Memcache\APCu',
```

Memory caching backend for locally stored data

- Used for host-specific data, e.g. file paths

Defaults to none

```
'memcache.distributed' => '\OC\Memcache\Memcached',
```

Memory caching backend for distributed data

- Used for installation-specific data, e.g. database caching
- If unset, defaults to the value of memcache.local

Defaults to none

```
'redis' => [
    'host' => 'localhost', // can also be a unix domain socket: '/tmp/redis.sock'
    'port' => 6379,
    'timeout' => 0.0,
    'password' => '', // Optional, if not defined no password will be used.
    'dbindex' => 0, // Optional, if undefined SELECT will not run and will use Redis
    ↪Server's default DB Index.
],
```

Connection details for redis to use for memory caching in a single server configuration.

For enhanced security it is recommended to configure Redis to require a password. See <http://redis.io/topics/security> for more information.

```
'redis.cluster' => [
    'seeds' => [ // provide some/all of the cluster servers to bootstrap discovery,
    ↪port required
        'localhost:7000',
        'localhost:7001',
    ],
    'timeout' => 0.0,
    'read_timeout' => 0.0,
    'failover_mode' => \RedisCluster::FAILOVER_ERROR,
    'password' => '', // Optional, if not defined no password will be used.
],
```

Connection details for a Redis Cluster

Only for use with Redis Clustering, for Sentinel-based setups use the single server configuration above, and perform HA on the hostname.

Redis Cluster support requires the php module phpredis in version 3.0.0 or higher.

Available failover modes:

- \RedisCluster::FAILOVER_NONE - only send commands to master nodes (default)
- \RedisCluster::FAILOVER_ERROR - failover to slaves for read commands if master is unavailable (recommended)
- \RedisCluster::FAILOVER_DISTRIBUTE - randomly distribute read commands across master and slaves

WARNING: FAILOVER_DISTRIBUTE is a not recommended setting and we strongly suggest to not use it if you use Redis for file locking. Due to the way Redis is synchronized it could happen, that the read for an existing lock is scheduled to a slave that is not fully synchronized with the connected master which then causes a FileLocked exception.

See <https://redis.io/topics/cluster-spec> for details about the Redis cluster

Authentication works with phpredis version 4.2.1+. See <https://github.com/phpredis/phpredis/commit/c5994f2a42b8a348af92d3acb4edff1328ad8ce1>

```
'memcached_servers' => [
    // hostname, port and optional weight. Also see:
    // https://www.php.net/manual/en/memcached.addservers.php
    // https://www.php.net/manual/en/memcached.addserver.php
    ['localhost', 11211],
    //array('other.host.local', 11211),
],
```

Server details for one or more memcached servers to use for memory caching.

```
'memcached_options' => [
    // Set timeouts to 50ms
    \Memcached::OPT_CONNECT_TIMEOUT => 50,
    \Memcached::OPT_RETRY_TIMEOUT => 50,
    \Memcached::OPT_SEND_TIMEOUT => 50,
    \Memcached::OPT_RECV_TIMEOUT => 50,
    \Memcached::OPT_POLL_TIMEOUT => 50,

    // Enable compression
    \Memcached::OPT_COMPRESSION => true,

    // Turn on consistent hashing
    \Memcached::OPT_LIBKETAMA_COMPATIBLE => true,

    // Enable Binary Protocol
    \Memcached::OPT_BINARY_PROTOCOL => true,

    // Binary serializer will be enabled if the igbinary PECL module is available
    \Memcached::OPT_SERIALIZER => \Memcached::SERIALIZER_IGBINARY,
],
```

Connection options for memcached

```
'cache_path' => '',
```

Location of the cache folder, defaults to data/\$user/cache where \$user is the current user. When specified, the format will change to \$cache_path/\$user where \$cache_path is the configured cache directory and \$user is the user.

Defaults to '' (empty string)

```
'cache_chunk_gc_ttl' => 60*60*24,
```

TTL of chunks located in the cache folder before they're removed by garbage collection (in seconds). Increase this value if users have issues uploading very large files via the Nextcloud Client as upload isn't completed within one day.

Defaults to 60*60*24 (1 day)

5.6.19 Using Object Store with Nextcloud

```
'objectstore' => [
    'class' => 'OC\\Files\\ObjectStore\\Swift',
    'arguments' => [
        // trystack will use your facebook id as the user name
        'username' => 'facebook100000123456789',
        // in the trystack dashboard go to user -> settings -> API Password to
        // generate a password
        'password' => 'Secr3tPaSSWoRdt7',
        // must already exist in the objectstore, name can be different
        'container' => 'nextcloud',
        // prefix to prepend to the fileid, default is 'oid:urn:'
        'objectPrefix' => 'oid:urn:',
    ],
],
```

(continues on next page)

(continued from previous page)

```

        // create the container if it does not exist. default is false
        'autocreate' => true,
        // required, dev-/trystack defaults to 'RegionOne'
        'region' => 'RegionOne',
        // The Identity / Keystone endpoint
        'url' => 'http://8.21.28.222:5000/v2.0',
        // required on dev-/trystack
        'tenantName' => 'facebook100000123456789',
        // dev-/trystack uses swift by default, the lib defaults to 'cloudFiles'
        // if omitted
        'serviceName' => 'swift',
        // The Interface / url Type, optional
        'urlType' => 'internal'
    ],
],

```

This example shows how to configure Nextcloud to store all files in a swift object storage.

It is important to note that Nextcloud in object store mode will expect exclusive access to the object store container because it only stores the binary data for each file. The metadata is currently kept in the local database for performance reasons.

WARNING: The current implementation is incompatible with any app that uses direct file IO and circumvents our virtual filesystem. That includes Encryption and Gallery. Gallery will store thumbnails directly in the filesystem and encryption will cause severe overhead because key files need to be fetched in addition to any requested file.

One way to test is applying for a trystack account at <http://trystack.org/>

```

'objectstore' => [
    'class' => 'OC\\Files\\ObjectStore\\Swift',
    'arguments' => [
        'autocreate' => true,
        'user' => [
            'name' => 'swift',
            'password' => 'swift',
            'domain' => [
                'name' => 'default',
            ],
        ],
    ],
    'scope' => [
        'project' => [
            'name' => 'service',
            'domain' => [
                'name' => 'default',
            ],
        ],
    ],
    'tenantName' => 'service',
    'serviceName' => 'swift',
    'region' => 'regionOne',
    'url' => 'http://yourswiftost:5000/v3',
    'bucket' => 'nextcloud',
],
],

```

To use swift V3

```
'objectstore.multibucket.preview-distribution' => false,
```

If this is set to true and a multibucket object store is configured then newly created previews are put into 256 dedicated buckets.

Those buckets are named like the multibucket version but with the postfix `-preview-NUMBER` where `NUMBER` is between 0 and 255.

Keep in mind that only previews of files are put in there that don't have some already. Otherwise the old bucket will be used.

To migrate existing previews to this new multibucket distribution of previews use the occ command `preview:repair`. For now this will only migrate previews that were generated before Nextcloud 19 in the flat `appdata_INSTANCEID/previews/FILEID` folder structure.

5.6.20 Sharing

Global settings for Sharing

```
'sharing.managerFactory' => '\OC\Share20\ProviderFactory',
```

Replaces the default Share Provider Factory. This can be utilized if own or 3rdParty Share Providers are used that – for instance – use the filesystem instead of the database to keep the share information.

Defaults to `\OC\Share20\ProviderFactory`

```
'sharing.maxAutocompleteResults' => 25,
```

Define max number of results returned by the search for auto-completion of users, groups, etc. The value must not be lower than 0 (for unlimited).

If more, different sources are requested (e.g. different user backends; or both users and groups), the value is applied per source and might not be truncated after collecting the results. I.e. more results can appear than configured here.

Default is 25.

```
'sharing.minSearchStringLength' => 0,
```

Define the minimum length of the search string before we start auto-completion Default is no limit (value set to 0)

```
'sharing.enable_share_accept' => false,
```

Set to true to enable that internal shares need to be accepted by the users by default.

Users can change this for their account in their personal sharing settings

```
'sharing.force_share_accept' => false,
```

Set to true to enforce that internal shares need to be accepted

```
'sharing.enable_share_mail' => true,
```

Set to false to stop sending a mail when users receive a share

5.6.21 All other configuration options

```
'dbdriveroptions' => [
    PDO::MYSQL_ATTR_SSL_CA => '/file/path/to/ca_cert.pem',
    PDO::MYSQL_ATTR_INIT_COMMAND => 'SET wait_timeout = 28800'
],
```

Additional driver options for the database connection, eg. to enable SSL encryption in MySQL or specify a custom wait timeout on a cheap hoster.

```
'sqlite.journal_mode' => 'DELETE',
```

sqlite3 journal mode can be specified using this configuration parameter - can be 'WAL' or 'DELETE' see for more details <https://www.sqlite.org/wal.html>

```
'mysql.utf8mb4' => false,
```

During setup, if requirements are met (see below), this setting is set to true and MySQL can handle 4 byte characters instead of 3 byte characters.

If you want to convert an existing 3-byte setup into a 4-byte setup please set the parameters in MySQL as mentioned below and run the migration command: `./occ db:convert-mysql-charset` The config setting will be set automatically after a successful run.

Consult the documentation for more details.

MySQL requires a special setup for longer indexes (> 767 bytes) which are needed:

```
[mysql] innodb_large_prefix=ON innodb_file_format=Barracuda innodb_file_per_table=ON
```

Tables will be created with

- character set: utf8mb4
- collation: utf8mb4_bin
- row_format: compressed

See: <https://dev.mysql.com/doc/refman/5.7/en/charset-unicode-utf8mb4.html> https://dev.mysql.com/doc/refman/5.7/en/innodb-parameters.html#sysvar_innodb_large_prefix https://mariadb.com/kb/en/mariadb-xtradbinnodb-server-system-variables/#innodb_large_prefix
<http://www.tocker.ca/2013/10/31/benchmarking-innodb-page-compression-performance.html> <http://mechanics.flite.com/blog/2014/07/29/using-innodb-large-prefix-to-avoid-error-1071/>

```
'supportedDatabases' => [
    'sqlite',
    'mysql',
    'pgsql',
    'oci',
],
```

Database types that are supported for installation.

Available:

- sqlite (SQLite3)
- mysql (MySQL)
- pgsql (PostgreSQL)

- oci (Oracle)

Defaults to the following databases:

- sqlite (SQLite3)
- mysql (MySQL)
- pgsql (PostgreSQL)

```
'tempdirectory' => '/tmp/nextcloudtemp',
```

Override where Nextcloud stores temporary files. Useful in situations where the system temporary directory is on a limited space ramdisk or is otherwise restricted, or if external storages which do not support streaming are in use.

The Web server user must have write access to this directory.

5.6.22 Hashing

```
'hashing_default_password' => false,
```

By default Nextcloud will use the Argon2 password hashing if available.

However if for whatever reason you want to stick with the PASSWORD_DEFAULT of your php version. Then set the setting to true.

Nextcloud uses the Argon2 algorithm (with PHP >= 7.2) to create hashes by its own and exposes its configuration options as following. More information can be found at: <https://www.php.net/manual/en/function.password-hash.php>

```
'hashingThreads' => PASSWORD_ARGON2_DEFAULT_THREADS,
```

The number of CPU threads to be used by the algorithm for computing a hash.

The value must be an integer, and the minimum value is 1. Rationally it does not help to provide a number higher than the available threads on the machine. Values that undershoot the minimum will be ignored in favor of the minimum.

```
'hashingMemoryCost' => PASSWORD_ARGON2_DEFAULT_MEMORY_COST,
```

The memory in KiB to be used by the algorithm for computing a hash. The value must be an integer, and the minimum value is 8 times the number of CPU threads.

Values that undershoot the minimum will be ignored in favor of the minimum.

```
'hashingTimeCost' => PASSWORD_ARGON2_DEFAULT_TIME_COST,
```

The number of iterations that are used by the algorithm for computing a hash.

The value must be an integer, and the minimum value is 1. Values that undershoot the minimum will be ignored in favor of the minimum.

```
'hashingCost' => 10,
```

The hashing cost used by hashes generated by Nextcloud Using a higher value requires more time and CPU power to calculate the hashes

```
'blacklisted_files' => ['.htaccess'],
```

Blacklist a specific file or files and disallow the upload of files with this name. `.htaccess` is blocked by default.

WARNING: USE THIS ONLY IF YOU KNOW WHAT YOU ARE DOING.

Defaults to `array('.htaccess')`

```
'share_folder' => '/',
```

Define a default folder for shared files and folders other than root.

Changes to this value will only have effect on new shares.

Defaults to `/`

```
'theme' => '',
```

If you are applying a theme to Nextcloud, enter the name of the theme here.

The default location for themes is `nextcloud/themes/`.

Defaults to the theming app which is shipped since Nextcloud 9

```
'cipher' => 'AES-256-CTR',
```

The default cipher for encrypting files. Currently supported are:

- AES-256-CTR
- AES-128-CTR
- AES-256-CFB
- AES-128-CFB

Defaults to `AES-256-CTR`

```
'minimum.supported.desktop.version' => '2.0.0',
```

The minimum Nextcloud desktop client version that will be allowed to sync with this server instance. All connections made from earlier clients will be denied by the server. Defaults to the minimum officially supported Nextcloud desktop client version at the time of release of this server version.

When changing this, note that older unsupported versions of the Nextcloud desktop client may not function as expected, and could lead to permanent data loss for clients or other unexpected results.

Defaults to `2.0.0`

```
'localstorage.allowsymlinks' => false,
```

Option to allow local storage to contain symlinks.

WARNING: Not recommended. This would make it possible for Nextcloud to access files outside the data directory and could be considered a security risk.

Defaults to `false`

```
'quota_include_external_storage' => false,
```

EXPERIMENTAL: option whether to include external storage in quota calculation, defaults to `false`.

Defaults to `false`

```
'external_storage.auth_availability_delay' => 1800,
```

When an external storage is unavailable for some reasons, it will be flagged as such for 10 minutes. When the trigger is a failed authentication attempt the delay is higher and can be controlled with this option. The motivation is to make account lock outs at Active Directories (and compatible) more unlikely.

Defaults to 1800 (seconds)

```
'filesystem_check_changes' => 0,
```

Specifies how often the local filesystem (the Nextcloud data/ directory, and NFS mounts in data/) is checked for changes made outside Nextcloud. This does not apply to external storages.

0 -> Never check the filesystem for outside changes, provides a performance increase when it's certain that no changes are made directly to the filesystem

1 -> Check each file or folder at most once per request, recommended for general use if outside changes might happen.

Defaults to 0

```
'part_file_in_storage' => true,
```

By default Nextcloud will store the part files created during upload in the same storage as the upload target. Setting this to false will store the part files in the root of the users folder which might be required to work with certain external storage setups that have limited rename capabilities.

Defaults to true

```
'mount_file' => '/var/www/nextcloud/data/mount.json',
```

Where mount.json file should be stored, defaults to data/mount.json in the Nextcloud directory.

Defaults to data/mount.json in the Nextcloud directory.

```
'filesystem_cache_readonly' => false,
```

When true, prevent Nextcloud from changing the cache due to changes in the filesystem for all storage.

Defaults to false

```
'secret' => '',
```

Secret used by Nextcloud for various purposes, e.g. to encrypt data. If you lose this string there will be data corruption.

```
'trusted_proxies' => ['203.0.113.45', '198.51.100.128', '192.168.2.0/24'],
```

List of trusted proxy servers

You may set this to an array containing a combination of - IPv4 addresses, e.g. 192.168.2.123 - IPv4 ranges in CIDR notation, e.g. 192.168.2.0/24 - IPv6 addresses, e.g. fd9e:21a7:a92c:2323::1

(CIDR notation for IPv6 is currently work in progress and thus not available as of yet)

When an incoming request's *REMOTE_ADDR* matches any of the IP addresses specified here, it is assumed to be a proxy instead of a client. Thus, the client IP will be read from the HTTP header specified in *forwarded_for_headers* instead of from *REMOTE_ADDR*.

So if you configure *trusted_proxies*, also consider setting *forwarded_for_headers* which otherwise defaults to *HTTP_X_FORWARDED_FOR* (the *X-Forwarded-For* header).

Defaults to an empty array.

```
'forwarded_for_headers' => ['HTTP_X_FORWARDED', 'HTTP_FORWARDED_FOR'],
```

Headers that should be trusted as client IP address in combination with *trusted_proxies*. If the HTTP header looks like 'X-Forwarded-For', then use 'HTTP_X_FORWARDED_FOR' here.

If set incorrectly, a client can spoof their IP address as visible to Nextcloud, bypassing access controls and making logs useless!

Defaults to 'HTTP_X_FORWARDED_FOR'

```
'max_filesize_animated_gifs_public_sharing' => 10,
```

max file size for animating gifs on public-sharing-site.

If the gif is bigger, it'll show a static preview

Value represents the maximum filesize in megabytes. Set to -1 for no limit.

Defaults to 10 megabytes

```
'filelocking.enabled' => true,
```

Enables transactional file locking.

This is enabled by default.

Prevents concurrent processes from accessing the same files at the same time. Can help prevent side effects that would be caused by concurrent operations. Mainly relevant for very large installations with many users working with shared files.

Defaults to true

```
'filelocking.ttl' => 60*60,
```

Set the lock's time-to-live in seconds.

Any lock older than this will be automatically cleaned up.

Defaults to 60*60 seconds (1 hour) or the php max_execution_time, whichever is higher.

```
'memcache.locking' => '\\OC\\Memcache\\Redis',
```

Memory caching backend for file locking

Because most memcache backends can clean values without warning using redis is highly recommended to *avoid data loss*.

Defaults to none

```
'filelocking.debug' => false,
```

Enable locking debug logging

Note that this can lead to a very large volume of log items being written which can lead to performance degradation and large log files on busy instance.

Thus enabling this in production for longer periods of time is not recommended or should be used together with the `log.condition` setting.

```
'upgrade.disable-web' => false,
```

Disable the web based updater

```
'debug' => false,
```

Set this Nextcloud instance to debugging mode

Only enable this for local development and not in production environments This will disable the minifier and outputs some additional debug information

Defaults to false

```
'data-fingerprint' => '',
```

Sets the data-fingerprint of the current data served

This is a property used by the clients to find out if a backup has been restored on the server. Once a backup is restored run `./occ maintenance:data-fingerprint` To set this to a new value.

Updating/Deleting this value can make connected clients stall until the user has resolved conflicts.

Defaults to '' (empty string)

```
'copied_sample_config' => true,
```

This entry is just here to show a warning in case somebody copied the sample configuration. DO NOT ADD THIS SWITCH TO YOUR CONFIGURATION!

If you, brave person, have read until here be aware that you should not modify *ANY* settings in this file without reading the documentation.

```
'lookup_server' => 'https://lookup.nextcloud.com',
```

use a custom lookup server to publish user data

```
'gs.enabled' => false,
```

set to true if the server is used in a setup based on Nextcloud's Global Scale architecture

```
'gs.federation' => 'internal',
```

by default federation is only used internally in a Global Scale setup If you want to allow federation outside of your environment set it to 'global'

```
'csrf.optout' => [
    '/^WebDAVFS/', // OS X Finder
    '/^Microsoft-WebDAV-MiniRedir/', // Windows webdav drive
],
```

List of incompatible user agents opted out from Same Site Cookie Protection.

Some user agents are notorious and don't really properly follow HTTP specifications. For those, have an opt-out.

WARNING: only use this if you know what you are doing

```
'simpleSignUpLink.shown' => true,
```

By default there is on public pages a link shown that allows users to learn about the "simple sign up" - see <https://nextcloud.com/signup/>

If this is set to "false" it will not show the link.

```
'login_form_autocomplete' => true,
```

By default autocompletion is enabled for the login form on Nextcloud's login page.

While this is enabled, browsers are allowed to “remember” login names and such. Some companies require it to be disabled to comply with their security policy.

Simply set this property to “false”, if you want to turn this feature off.

```
'files_no_background_scan' => false,
```

Disable background scanning of files

By default, a background job runs every 10 minutes and execute a background scan to sync filesystem and database. Only users with unscanned files (size < 0 in filecache) are included. Maximum 500 users per job.

Defaults to true

5.6.23 App config options

Activity app

Retention for activities of the activity app:

```
'activity_expire_days' => 365,
```

Every day a cron job is ran, which deletes all activities for all users which are older then the number of days that is set for `activity_expire_days`

```
'activity_use_cached_mountpoints' => false,
```

Before enabling this, read the warning in *Activities in groupfolders*

Settings app

If an email address of a user is changed by an admin, then it triggers an email to the user that states “Your email address on URL was changed by an administrator”. In some cases this should not be triggered, because it was a normal maintenance change. To disable this specific email the appconfig option `disable_email.email_address_changed_by_admin` can be set to yes:

```
occ config:app:set settings disable_activity.email_address_changed_by_admin --value yes
```

To disable this behaviour change it to any other value or delete the app config:

```
occ config:app:delete settings disable_activity.email_address_changed_by_admin
```

5.7 Email

Nextcloud is capable of sending password reset emails, notifying users of new file shares, changes in files, and activity notifications. Your users configure which notifications they want to receive on their Personal pages.

Nextcloud does not contain a full email server, but rather connects to your existing mail server. You must have a functioning mail server for Nextcloud to be able to send emails. You may have a mail server on the same machine as Nextcloud, or it may be a remote server.

Email server *i*

It is important to set up this server to be able to send emails, like for password reset and notifications.

The screenshot shows the 'Email server' configuration wizard in Nextcloud. It contains the following fields and controls:

- Send mode:** A dropdown menu set to 'SMTP'.
- Encryption:** A dropdown menu set to 'SSL/TLS'.
- From address:** A text input field containing 'noreply' followed by an '@' symbol and another text input field containing 'cloud.example.inc'.
- Authentication method:** A dropdown menu set to 'Login'.
- Authentication required:** A checkbox that is checked, with the label 'Authentication required'.
- Server address:** A text input field containing '172.17.0.1' followed by a colon ':' and a text input field containing 'Port'.
- Credentials:** Two text input fields, 'SMTP Username' and 'SMTP Password'.
- Buttons:** A 'Test email settings' button, a 'Send email' button, and a 'Store credentials' button.

With the wizard, connecting Nextcloud to your mail server is fast and easy. The wizard fills in the values in `config/config.php`, so you may use either or both as you prefer.

The Nextcloud Email wizard supports three types of mail server connections: SMTP, qmail, and Sendmail. Use the SMTP configurator for a remote server or Sendmail when your mail server is on the same machine as Nextcloud.

Note: The Sendmail option refers to the Sendmail SMTP server and any drop-in Sendmail replacement such as Postfix, Exim, or Courier. All of these include a `sendmail` binary, and are freely-interchangeable.

5.7.1 Configuring an SMTP server

You need the following information from your mail server administrator to connect Nextcloud to a remote SMTP server:

- Encryption type: None, SSL/TLS, or STARTTLS
- The From address you want your outgoing Nextcloud mails to use
- Whether authentication is required
- Authentication method: None, Login, Plain, or NT LAN Manager
- The server's IP address or fully-qualified domain name and the SMTP port
- Login credentials (if required)

Email server *i*

This is used for sending out notifications.

Send mode smtp Encryption None

From address nextcloud @ alrac.net

Authentication method ☒ Login ☐ Plain ☐ NT LAN Manager

Server address nextcloud : 25

Credentials nextcloud

Store credentials

Your changes are saved immediately, and you can click the Send Email button to test your configuration. This sends a test message to the email address you configured on your Personal page. The test message says:

If you received this email, the settings seem to be correct.

--

Nextcloud
a safe home **for** all your data

5.7.2 Configuring Sendmail/qmail

Configuring Sendmail or qmail requires only that you select one of them instead of SMTP, and then enter your desired return email address.

In most cases the SMTP option is best, since you will be able to control all of your mail server options in one place, in your mail server configuration then.

5.7.3 Using email templates

We designed a mechanism that generates emails which follow the theming settings and look the same in all the different email clients out there.

Note: If, for some reason, you need text-only emails, consider simply configuring this on the client side or let the receiving (or even sending) mail server drop the HTML part. Note that there is no security impact from **sending** HTML emails, just from displaying them and thus any security risk can only be mitigated by disabling showing HTML on the client (or removing the HTML part in the mail server).

Modifying the look of emails beyond the theming app capabilities

You can overwrite templates by writing a class that implements the template interface (or extends it to not need to copy over everything). Easiest way is to then put this class into an app and load it so you do not need to patch it on every update.

This is the interface of the class that needs to be implemented: <https://github.com/nextcloud/server/blob/master/lib/public/Mail/IEmailTemplate.php>

That is the implementation that could be extended and used to see how it works: <https://github.com/nextcloud/server/blob/master/lib/private/Mail/EmailTemplate.php>

An example from a [GitHub issue](#):

1. Look at the source code of extended class `OC\Mail\EmailTemplate::class`
2. Then override what you need in your own `OC\Mail\EmailTemplate::class` extension

Example:

Let's assume that we need to override the email header:

```
<?php
namespace \OCA\MyApp;

use OC\Mail\EmailTemplate;

class MyClass extends EmailTemplate
{
    protected $header = <<<EOF
        <table align="center" class="wrapper">
            // your theme email header modification
        </table>
    EOF;
}
```

3. Then in `config/config.php` change `mail_template_class` to your class namespace:

```
'mail_template_class' => 'OCA\MyApp\MyClass',
```

You will find a detailed step by step guide in our [support portal](#).

5.7.4 Setting mail server parameters in config.php

If you prefer, you may set your mail server parameters in `config/config.php`. The following examples are for SMTP, Sendmail, and Qmail.

SMTP

If you want to send email using a local or remote SMTP server it is necessary to enter the name or IP address of the server, optionally followed by a colon separated port number, e.g. **:425**. If this value is not given the default port 25/tcp will be used unless you change that by modifying the **mail_smtpport** parameter.

```
"mail_smtpmode"    => "smtp",  
"mail_smtphost"    => "smtp.server.dom:425",
```

or

```
"mail_smtpmode"    => "smtp",  
"mail_smtphost"    => "smtp.server.dom",  
"mail_smtpport"    => 425,
```

If a malware or SPAM scanner is running on the SMTP server it might be necessary that you increase the SMTP timeout to e.g. 30s:

```
"mail_smtptimeout" => 30,
```

If the SMTP server accepts insecure connections, the default setting can be used:

```
"mail_smtpsecure"  => '',
```

If the SMTP server only accepts secure connections you can choose between the following two variants:

SSL

A secure connection will be initiated using the outdated SMTPS protocol which uses the port 465/tcp:

```
"mail_smtphost"    => "smtp.server.dom:465",  
"mail_smtpsecure"  => 'ssl',
```

TLS

A secure connection will be initiated using the STARTTLS protocol which uses the default port 25/tcp:

```
"mail_smtphost"    => "smtp.server.dom",  
"mail_smtpsecure"  => 'tls',
```

And finally it is necessary to configure if the SMTP server requires authentication, if not, the default values can be taken as is.

```
"mail_smtpauth"    => false,  
"mail_smtpname"    => "",  
"mail_smtppassword" => "",
```

If SMTP authentication is required you have to set the required username and password and can optionally choose between the authentication types **LOGIN** (default) or **PLAIN**.

```
"mail_smtpauth"    => true,  
"mail_smtpauthtype" => "LOGIN",  
"mail_smtpname"    => "username",  
"mail_smtppassword" => "password",
```

Advanced users can add additional stream options in `config/config.php`, which maps directly to [Swift Mailer's](#) `streamOptions` configuration parameter:

```
"mail_smtpstreamoptions" => array(),
```

Sendmail

If you want to use the well known Sendmail program to send email, it is necessary to have an installed and working email system on your *nix server. The sendmail binary (`/usr/sbin/sendmail`) is usually part of that system. Nextcloud should be able to send email out of the box.

```
"mail_smtpmode"      => "sendmail",
"mail_smtphost"      => "127.0.0.1",
"mail_smtpport"      => 25,
"mail_smtptimeout"   => 10,
"mail_smtpsecure"    => "",
"mail_smtpauth"      => false,
"mail_smtpauthtype"  => "LOGIN",
"mail_smtpname"      => "",
"mail_smtppassword"  => "",
```

qmail

If you want to use the qmail program to send email, it is necessary to have an installed and working qmail email system on your server. The qmail binary installed on your server will then be used to send email. Nextcloud should be able to send email out of the box.

```
"mail_smtpmode"      => "qmail",
"mail_smtphost"      => "127.0.0.1",
"mail_smtpport"      => 25,
"mail_smtptimeout"   => 10,
"mail_smtpsecure"    => "",
"mail_smtpauth"      => false,
"mail_smtpauthtype"  => "LOGIN",
"mail_smtpname"      => "",
"mail_smtppassword"  => "",
```

5.7.5 Send a test email

To test your email configuration, save your email address in your personal settings and then use the **Send email** button in the *Email Server* section of the Admin settings page.

5.7.6 Troubleshooting

If you are unable to send email, try turning on debugging. Do this by enabling the `mail_smtpdebug` parameter in `config/config.php`.

```
"mail_smtpdebug" => true;
```

Note: Immediately after pressing the **Send email** button, as described before, several **SMTP -> get_lines(): ...** messages appear on the screen. This is expected behavior and can be ignored.

Question: Why is my web domain different from my mail domain?

Answer: The default domain name used for the sender address is the hostname where your Nextcloud installation is served. If you have a different mail domain name you can override this behavior by setting the following configuration parameter:

```
"mail_domain" => "example.com",
```

This setting results in every email sent by Nextcloud (for example, the password reset email) having the domain part of the sender address appear as follows:

```
no-reply@example.com
```

Question: How can I find out if an SMTP server is reachable?

Answer: Use the ping command to check the server availability:

```
ping smtp.server.dom
```

```
PING smtp.server.dom (ip-address) 56(84) bytes of data.  
64 bytes from your-server.local.lan (192.168.1.10): icmp_req=1 ttl=64  
time=3.64ms
```

Question: How can I find out if the SMTP server is listening on a specific TCP port?

Answer: The best way to get mail server information is to ask your mail server admin. If you are the mail server admin, or need information in a hurry, you can use the `netstat` command. This example shows all active servers on your system, and the ports they are listening on. The SMTP server is listening on localhost port 25.

```
# netstat -pant
```

```
Active Internet connections (servers and established)
Proto Recv-Q Send-Q Local Address   Foreign Address State    ID/Program name
tcp      0      0 0.0.0.0:631     0.0.0.0:*       LISTEN  4418/cupsd
tcp      0      0 127.0.0.1:25    0.0.0.0:*       LISTEN  2245/exim4
tcp      0      0 127.0.0.1:3306  0.0.0.0:*       LISTEN  1524/mysqld
```

- 25/tcp is unencrypted smtp
- 110/tcp/udp is unencrypted pop3
- 143/tcp/udp is unencrypted imap4
- 465/tcp is encrypted ssmtp
- 993/tcp/udp is encrypted imaps

- 995/tcp/udp is encrypted pop3s

Question: How can I determine if the SMTP server supports the outdated SMTPS protocol?

Answer: A good indication that the SMTP server supports the SMTPS protocol is that it is listening on port **465**.

Question: How can I determine what authorization and encryption protocols the mail server supports?

Answer: SMTP servers usually announce the availability of STARTTLS immediately after a connection has been established. You can easily check this using the `telnet` command.

Note: You must enter the marked lines to obtain the information displayed.

```
telnet smtp.domain.dom 25
```

```
Trying 192.168.1.10...
Connected to smtp.domain.dom.
Escape character is '^]'.
220 smtp.domain.dom ESMTP Exim 4.80.1 Tue, 22 Jan 2013 22:39:55 +0100
EHLO your-server.local.lan          # <<< enter this command
250-smtp.domain.dom Hello your-server.local.lan [ip-address]
250-SIZE 52428800
250-8BITMIME
250-PIPELINING
250-AUTH PLAIN LOGIN CRAM-MD5        # <<< Supported auth protocols
250-STARTTLS                        # <<< Encryption is supported
250 HELP
QUIT                                # <<< enter this command
221 smtp.domain.dom closing connection
Connection closed by foreign host.
```

Question: How can I send mail when using self-signed certificates if remote SMTP server do not have options to allow this on their side?

Answer: If you are having remote SMTP setup, you can try adding this to your `config/config.php`:

```
"mail_smtpstreamoptions" => array(
    'ssl' => array(
        'allow_self_signed' => true,
        'verify_peer' => false,
        'verify_peer_name' => false
    )
),
```

5.7.7 Enabling debug mode

If you are unable to send email, it might be useful to activate further debug messages by enabling the `mail_smtpdebug` parameter:

```
"mail_smtpdebug" => true,
```

Note: Immediately after pressing the **Send email** button, as described before, several `SMTP -> get_lines(): ...`

messages appear on the screen. This is expected behavior and can be ignored.

5.8 Linking external sites

You can embed external websites or documents inside your Nextcloud pages with the **External sites** app, as this screenshot shows.




Fig. 1: *Click to enlarge*

This is useful for quick access to important pages such as the Nextcloud manuals and informational pages for your company, and for presenting external pages inside your custom Nextcloud branding, if you use your own custom themes.

The External sites app can be easily installed from the app store. Go to **Settings > Apps > Customization** to enable it. Then go to your Nextcloud **Settings > Administration > External sites** to create your links, which are saved automatically.

Each link can have a unique icon, which can be uploaded in the admin settings. If you select a language, the link will only be displayed for users with the selected language. This allows you to have different documentation links for users depending on their language.

It is also possible to add links for a special device (recognized by the user agent). Currently the following options are available: All devices, Android app, iOS app, Desktop client and all others (Browsers).

It is also possible to add links only for members of a given group.





Fig. 2: Click to enlarge


The links appear in the Nextcloud menu on the top or in the settings menu, after reloading the page.



5.8.1 Configurations preventing embedding

Your links may or may not work correctly due to the various ways that Web browsers and Web sites handle HTTP and HTTPS URLs, and because the External Sites app embeds external links in IFrames. Modern Web browsers try very hard to protect Web surfers from dangerous links, and safety apps like [Privacy Badger](#) and ad-blockers may block embedded pages. It is strongly recommended to enforce HTTPS on your Nextcloud server; do not weaken this, or any of your security tools, just to make embedded Web pages work. After all, you can freely access them outside of Nextcloud.

Most Web sites that offer login functionalities use the X-Frame-Options or Content-Security-Policy HTTP header which instructs browsers to not allow their pages to be embedded for security reasons (e.g. “Clickjacking”). You can usually verify the reason why embedding the website is not possible by using your browser’s console tool. For example, this page has an invalid SSL certificate.



On this page, X-Frame-Options prevents the embedding.



There is also a redirect option, which allows that those websites can still be added for quick access. Instead of embedding the website the user will be redirected to it.

5.9 Language & Locale

5.9.1 Default language

In normal cases Nextcloud will automatically detect the language of the Web-GUI. If this does not work properly or you want to make sure that Nextcloud always starts with a given language, you can set a **default_language** parameter in the `config/config.php`.

Note: The `default_language` parameter is only used, when the browser does not send any language, and the user hasn't configured own language preferences.

```
"default_language" => "en",
```

5.9.2 Force language

If you want to force a specific language, users will no longer be able to change their language in the personal settings. You can set a **force_language** parameter in the `config/config.php`.

```
"force_language" => "en",
```

If users shall be unable to change their language, but users have different languages, this value can be set to `true` instead of a language code.

Note: Please check [Transifex language codes](#) for the list of valid language codes.

5.9.3 Default locale

The locale is used to define how dates and other formats are displayed. Nextcloud should automatically pick an appropriate locale based on your current language. Users can modify their locale inside their settings panel. If that does not work properly or if you want to make sure that Nextcloud always starts with a given locale, you can set a **default_locale** parameter in the `config/config.php`.

Note: The `default_locale` parameter is only used when the user hasn't configured own locale preferences.

```
"default_locale" => "en_US",
```

5.9.4 Force locale

If you want to force a specific locale, users will no longer be able to change their locale in the personal settings. You can set a **force_locale** parameter in the `config/config.php`.

```
"force_locale" => "en_US",
```

Note: Please check [the list of MomentJS supported locales](#) for the list of valid locales.

5.10 Logging

Use your Nextcloud log to review system status, or to help debug problems. You may adjust logging levels, and choose between using the Nextcloud log or your syslog. If additional audit information is required, you can optionally activate the **admin_audit** app, which by default generates a separate audit.log file in the data directory.

5.10.1 Log level

Logging levels range from **DEBUG**, which logs all activity, to **FATAL**, which logs only fatal errors.

- **0**: **DEBUG**: All activity; the most detailed logging.
- **1**: **INFO**: Activity such as user logins and file activities, plus warnings, errors, and fatal errors.
- **2**: **WARN**: Operations succeed, but with warnings of potential problems, plus errors and fatal errors.
- **3**: **ERROR**: An operation fails, but other services and operations continue, plus fatal errors.
- **4**: **FATAL**: The server stops.

By default the log level is set to **2** (**WARN**). Use **DEBUG** when you have a problem to diagnose, and then reset your log level to a less-verbose level as **DEBUG** outputs a lot of information, and can affect your server performance.

Logging level parameters are set in the config/config.php file.

5.10.2 Log type

errorlog

All log information will be sent to PHP `error_log()`.

```
"log_type" => "errorlog",
```

file

All log information will be written to a separate log file which can be viewed using the log viewer on your Admin page. By default, a log file named **nextcloud.log** will be created in the directory which has been configured by the **datadirectory** parameter in config/config.php.

The desired date format can optionally be defined using the **logdateformat** parameter in config/config.php. By default the **PHP date function** parameter `c` is used, and therefore the date/time is written in the format `2013-01-10T15:20:25+02:00`. By using the date format in the example below, the date/time format will be written in the format `January 10, 2013 15:20:25`.

```
"log_type" => "file",  
"logfile" => "nextcloud.log",  
"loglevel" => 3,  
"logdateformat" => "F d, Y H:i:s",
```

syslog

All log information will be sent to your default syslog daemon.

```
"log_type" => "syslog",
"syslog_tag" => "Nextcloud",
"logfile" => "",
"loglevel" => 3,
```

systemd

All log information will be sent to Systemd journal. Requires [php-systemd](#) extension.

```
"log_type" => "systemd",
"syslog_tag" => "Nextcloud",
```

5.10.3 Log fields explained

Example log entries

```
{
  "reqId":"TBsuA2uE86DiOD0S8f9j",
  "level":1,
  "time":"April 13, 2021 16:55:37",
  "remoteAddr":"192.168.56.1",
  "user":"admin",
  "app":"admin_audit",
  "method":"GET",
  "url":"/ocs/v1.php/cloud/users?disabled",
  "message":"Login successful: \"admin\"",
  "userAgent":"curl/7.68.0",
  "version":"21.0.1.1"
}

{
  "reqId":"ByeDVLuwkXKMfLpBgvxC",
  "level":2,
  "time":"April 14, 2021 09:03:29",
  "remoteAddr":"192.168.56.1",
  "user":"--",
  "app":"no app in context",
  "method":"POST",
  "url":"/login",
  "message":"Login failed: asdf (Remote IP: 192.168.56.1)",
  "userAgent":"Mozilla/5.0 (X11; Linux x86_64) AppleWebKit/537.36 (KHTML, like Gecko)
↳ Chrome/89.0.4389.114 Safari/537.36",
  "version":"21.0.1.1"
}
```

Log field breakdown

- **0**: DEBUG: All activity; the most detailed logging.
- **reqId** (request id): any log lines related to a single request have the same value
- **level**: logged incident's level, always 1 in audit.log
- **time**: date and time (format and timezone can be configured in config.php)
- **remoteAddr**: the IP address of the user (if applicable – empty for occ commands)
- **user**: acting user's id (if applicable)
- **app**: affected app (always admin_audit in audit.log)
- **method**: HTTP method, for example GET, POST, PROPFIND, etc. – empty on occ calls
- **url**: request path (if applicable – empty on occ calls)
- **message**: event information
- **userAgent**: user agent (if applicable – empty on occ calls)
- **version**: Nextcloud version at the time of request

Empty value are written as two dashes: “--”.

5.10.4 Admin audit log

If `loglevel` in `config.php` is set to 2 or higher, audit logging needs to be triggered explicitly by adding the following setting to `config.php`:

```
'log.condition' => [  
    'apps' => ['admin_audit'],  
],
```

If required, the name and path of the audit log file can be customized by using the following command:

```
occ config:app:set admin_audit logfile --value=/var/log/nextcloud/audit.log
```

Find detailed documentation on auditable events for enterprises in our [customer portal](#).

5.10.5 Temporary overrides

You can run override the `config.php` log level of occ commands with as [documented here](#).

5.11 Antivirus scanner

You can configure your Nextcloud server to automatically run a virus scan on newly-uploaded files with the Antivirus app for Files. The Antivirus app for Files integrates the open source anti-virus engine [ClamAV](#) with Nextcloud. ClamAV detects all forms of malware including Trojan horses, viruses, and worms, and it operates on all major file types including Windows, Linux, and Mac files, compressed files, executables, image files, Flash, PDF, and many others. ClamAV's Freshclam daemon automatically updates its malware signature database at scheduled intervals.

ClamAV runs on Linux and any Unix-type operating system, and Microsoft Windows. However, it has only been tested with Nextcloud on Linux, so these instructions are for Linux systems. You must first install ClamAV, and then install and configure the Antivirus app for Files on Nextcloud.

5.11.1 Installing ClamAV

As always, the various Linux distributions manage installing and configuring ClamAV in different ways.

Debian, Ubuntu, Linux Mint On Debian and Ubuntu systems, and their many variants, install ClamAV with these commands:

```
apt-get install clamav clamav-daemon
```

The installer automatically creates default configuration files and launches the `clamd` and `freshclam` daemons. You don't have to do anything more, though it's a good idea to review the ClamAV documentation and your settings in `/etc/clamav/`. Enable verbose logging in both `clamd.conf` and `freshclam.conf` until you get any kinks worked out.

RedHat Enterprise Linux 7, CentOS 7 On RedHat Enterprise Linux 7 and related systems you must install the Extra Packages for Enterprise Linux (EPEL) repository, and then install ClamAV:

```
yum install epel-release
yum install clamav clamav-scanner clamav-scanner-systemd clamav-server
clamav-server-systemd clamav-update
```

This installs two configuration files: `/etc/freshclam.conf` and `/etc/clamd.d/scan.conf`. You must edit both of these before you can run ClamAV. Both files are well-commented, and `man clamd.conf` and `man freshclam.conf` explain all the options. Refer to `/etc/passwd` and `/etc/group` when you need to verify the ClamAV user and group.

First edit `/etc/freshclam.conf` and configure your options. `freshclam` updates your malware database, so you want it to run frequently to get updated malware signatures. Run it manually post-installation to download your first set of malware signatures:

```
freshclam
```

The EPEL packages do not include an init file for `freshclam`, so the quick and easy way to set it up for regular checks is with a cron job. This example runs it every hour at 47 minutes past the hour:

```
# m h dom mon dow command
47 * * * * /usr/bin/freshclam --quiet
```

Please avoid any multiples of 10, because those are when the ClamAV servers are hit the hardest for updates.

Next, edit `/etc/clamd.d/scan.conf`. When you're finished you must enable the `clamd` service file and start `clamd`:

```
systemctl enable clamd@scan.service
systemctl start clamd@scan.service
```

That should take care of everything. Enable verbose logging in `scan.conf` and `freshclam.conf` until it is running the way you want.

Docker, Docker-compose To install ClamAV via docker or docker compose you can take one of unofficial images of ClamAV, or build one by yourself. This example is based on docker image from <https://github.com/UKHomeOffice/docker-clamav>.

You can mount ClamAV Socket from the Docker Container to the host System as volume. In this case you do not need to expose any port outside of container. Also you need to edit config files as described above and added configuration for a local Socket. In this particular Image configuration parameters could be passed via `CLAMD_SETTINGS_CSV`.

For a Docker run this command:


```
docker run --name clamav -d -v /var/run/clamav:/var/run/clamav/ -e CLAMD_SETTINGS_CSV=
↪ "LocalSocket=/var/run/clamav/clamdctl" quay.io/ukhomeofficedigital/clamav:latest
```

For a Docker-compose use following settings:

```
version: "3.6"
services:
  clamav:
    image: "quay.io/ukhomeofficedigital/clamav:latest"
    container_name: "clamav"
    volumes:
      - /var/run/clamav:/var/run/clamav/
    restart: unless-stopped
    environment:
      - CLAMD_SETTINGS_CSV=LocalSocket=/var/run/clamav/clamdctl
```

5.11.2 Enabling the antivirus app for files

Place the `files_antivirus` app into the `apps` directory of your Nextcloud server. Then the app shows up on the Nextcloud Apps page where it simply can be enabled.



5.11.3 Configuring ClamAV on Nextcloud

Next, go to your Nextcloud Admin page and set your Nextcloud logging level to Everything.

What to log Everything (fatal issues, errors, warnings, info, debug) ▼

Now find your Antivirus Configuration panel on your Admin page.

Antivirus Configuration

Mode Daemon (Socket) ▾

Socket /var/run/clamav/clamd

Stream Length 10485760 bytes

Action for infected files found while scanning ✓ Only log
Delete file

Save

ClamAV runs in one of three modes:

- **Daemon (Socket):** ClamAV is running on the same server as Nextcloud. The ClamAV daemon, `clamd`, runs in the background. When there is no activity `clamd` places a minimal load on your system. If your users upload large volumes of files you will see high CPU usage.
- **Daemon:** ClamAV is running on a different server. This is a good option for Nextcloud servers with high volumes of file uploads.
- **Executable:** ClamAV is running on the same server as Nextcloud, and the `clamscan` command is started and then stopped with each file upload. `clamscan` is slow and not always reliable for on-demand usage; it is better to use one of the daemon modes.

Daemon (Socket) Nextcloud should detect your `clamd` socket and fill in the Socket field. This is the `LocalSocket` option in `clamd.conf`. You can run `netstat` to verify:

```
netstat -a|grep clam
unix 2 [ ACC ] STREAM LISTENING 15857 /var/run/clamav/clamdctl
```

Antivirus Configuration

Mode Daemon (Socket) ▾

Socket /var/run/clamav/clamd

Stream Length 10485760 bytes

Action for infected files found while scanning Only log ▾


Save

The **Stream Length** value sets the number of bytes read in one pass. 10485760 bytes, or ten megabytes, is the default. This value should be no larger than the PHP `memory_limit` settings, or physical memory if `memory_limit` is set to -1 (no limit).

Action for infected files found while scanning gives you the choice of logging any alerts without deleting the files, or immediately deleting infected files.

Daemon For the Daemon option you need the hostname or IP address of the remote server running ClamAV, and the server's port number.

Antivirus Configuration



Mode Daemon ▼

Host

Port


Stream Length bytes

Action for infected files found while scanning Only log ▼

Save

Executable The Executable option requires the path to `clamscan`, which is the interactive ClamAV scanning command. Nextcloud should find it automatically.

Antivirus Configuration



Mode Executable ▼

Stream Length bytes

Path to clamscan

Extra command line options (comma-separated)

Action for infected files found while scanning Only log ▼

Save

When you are satisfied with how ClamAV is operating, you might want to go back and change all of your logging to less verbose levels.

5.12 Reverse proxy

Nextcloud can be run through a reverse proxy, which can cache static assets such as images, CSS or JS files, move the load of handling HTTPS to a different server or load balance between multiple servers.

5.12.1 Defining trusted proxies

For security, you must explicitly define the proxy servers that Nextcloud is to trust. Connections from trusted proxies will be specially treated to get the real client information, for use in access control and logging. Parameters are configured in `config/config.php`

Set the `trusted_proxies` parameter as an array of:

- IPv4 addresses,
- IPv4 ranges in CIDR notation
- IPv6 addresses

to define the servers Nextcloud should trust as proxies. This parameter provides protection against client spoofing, and you should secure those servers as you would your Nextcloud server.

A reverse proxy can define HTTP headers with the original client IP address, and Nextcloud can use those headers to retrieve that IP address. Nextcloud uses the de-facto standard header 'X-Forwarded-For' by default, but this can be configured with the `forwarded_for_headers` parameter. This parameter is an array of PHP lookup strings, for example 'X-Forwarded-For' becomes 'HTTP_X_FORWARDED_FOR'. Incorrectly setting this parameter may allow clients to spoof their IP address as visible to Nextcloud, even when going through the trusted proxy! The correct value for this parameter is dependent on your proxy software.

5.12.2 Overwrite parameters

The automatic hostname, protocol or webroot detection of Nextcloud can fail in certain reverse proxy situations. This configuration allows the automatic detection to be manually overridden. If Nextcloud fails to automatically detect the hostname, protocol or webroot you can use the **overwrite** parameters inside the `config/config.php`.

- `overwritehost` set the hostname of the proxy. You can also specify a port.
- `overwriteprotocol` set the protocol of the proxy. You can choose between the two options **http** and **https**.
- `overwritewebroot` set the absolute web path of the proxy to the Nextcloud folder.
- `overwritecondaddr` overwrite the values dependent on the remote address. The value must be a **regular expression** of the IP addresses of the proxy. This is useful when you use a reverse SSL proxy only for https access and you want to use the automatic detection for http access.

Leave the value empty or omit the parameter to keep the automatic detection.

5.12.3 Service Discovery

The redirects for CalDAV or CardDAV does not work if Nextcloud is running behind a reverse proxy. The recommended solution is that your reverse proxy does the redirects.

Apache2

```
RewriteEngine On
RewriteRule ^/\..well-known/carddav https://%{SERVER_NAME}/remote.php/dav/ [R=301,L]
RewriteRule ^/\..well-known/caldav https://%{SERVER_NAME}/remote.php/dav/ [R=301,L]
```

Thanks to [@ffried](#) for apache2 example.

Traefik 1

Using docker tags:

```
traefik.frontend.redirect.permanent: 'true'
traefik.frontend.redirect.regex: https://(.*)/\..well-known/(card|cal)dav
traefik.frontend.redirect.replacement: https://$1/remote.php/dav/
```

Using traefik.toml:

```
[frontends.frontend1.redirect]
  regex = "https://(.*)/\..well-known/(card|cal)dav"
  replacement = "https://$1/remote.php/dav/"
  permanent = true
```

Thanks to [@pauvos](#) and [@mrtumnus](#) for traefik examples.

Traefik 2

```
[http.middlewares]
[http.middlewares.nextcloud-redirectregex.redirectRegex]
  permanent = true
  regex = "https://(.*)/\..well-known/(card|cal)dav"
  replacement = "https://${1}/remote.php/dav/"
```

HAProxy

```
acl url_discovery path /.well-known/caldav /.well-known/carddav
http-request redirect location /remote.php/dav/ code 301 if url_discovery
```

NGINX

```
location /.well-known/carddav {
    return 301 $scheme://$host/remote.php/dav;
}

location /.well-known/caldav {
    return 301 $scheme://$host/remote.php/dav;
}
```

or

```
rewrite ^/\.well-known/carddav https://$server_name/remote.php/dav/ redirect;
rewrite ^/\.well-known/caldav https://$server_name/remote.php/dav/ redirect;
```

Caddy

```
subdomain.example.com {
    rewrite /.well-known/carddav /remote.php/dav
    rewrite /.well-known/caldav /remote.php/dav

    reverse_proxy {$NEXTCLOUD_HOST:localhost}
}
```

5.12.4 Example

Multiple domains reverse SSL proxy

If you want to access your Nextcloud installation **http://domain.tld/nextcloud** via a multiple domains reverse SSL proxy **https://ssl-proxy.tld/domain.tld/nextcloud** with the IP address **10.0.0.1** you can set the following parameters inside the config/config.php.

```
<?php
$CONFIG = array (
    'trusted_proxies' => ['10.0.0.1'],
    'overwritehost' => 'ssl-proxy.tld',
    'overwriteprotocol' => 'https',
    'overwritewebroot' => '/domain.tld/nextcloud',
    'overwritecondaddr' => '^10\.0\.0\.1$',
);
```

Note: If you want to use the SSL proxy during installation you have to create the config/config.php otherwise you have to extend the existing \$CONFIG array.

5.13 Brute force protection

Nextcloud has built-in protection against brute force attempts. This protects your system from attackers trying for example a lot of different passwords.

Brute force protection is enabled by default on Nextcloud.

5.13.1 How it works

The brute force protection is easiest to see in action at the login page. If you try to log in the first time with an invalid username and/or password you will not notice anything. But if you do this a few times you start to notice that the verification of the login is taking longer each time. This is the brute force protection kicking in.

The maximum delay is 25 seconds.

After a successful login the attempts will be cleared. And once a user is properly authenticated they will not longer be hit by the delay.

5.13.2 Troubleshooting

On most setups Nextcloud will work out of the box without any issues. If you run into a situation where login is often very slow for all users the first step is to inspect the *bruteforce_attempts* table. There you can see which IP addresses are actually throttled.

If you are behind a reverse proxy or load balancer it is important you make sure it is setup properly. Especially the **trusted_proxies** and **forwarded_for_headers** *config.php* variables need to be set correctly. Otherwise it can happen that Nextcloud actually starts throttling all traffic coming from the reverse proxy or load balancer. For more information see [Reverse proxy](#).

5.14 Automatic setup

If you need to install Nextcloud on multiple servers, you normally do not want to set up each instance separately as described in [Database configuration](#). For this reason, Nextcloud provides an automatic configuration feature.

To take advantage of this feature, you must create a configuration file, called *config/autoconfig.php*, and set the file parameters as required. You can specify any number of parameters in this file. Any unspecified parameters appear on the “Finish setup” screen when you first launch Nextcloud.

The *config/autoconfig.php* is automatically removed after the initial configuration has been applied.

Note: Keep in mind that the automatic configuration does not eliminate the need for creating the database user and database in advance, as described in [Database configuration](#).

5.14.1 Parameters

When configuring parameters, you must understand that two parameters are named differently in this configuration file when compared to the standard `config.php` file.

autoconfig.php	config.php
directory	datadirectory
dbpass	dbpassword

5.14.2 Automatic configurations examples

The following sections provide sample automatic configuration examples and what information is requested at the end of the configuration.

Data Directory

Using the following parameter settings, the “Finish setup” screen requests database and admin credentials settings.

```
<?php
$AUTOCONFIG = [
    "directory"    => "/www/htdocs/nextcloud/data",
];
```

SQLite database

Using the following parameter settings, the “Finish setup” screen requests data directory and admin credentials settings.

```
<?php
$AUTOCONFIG = [
    "dbtype"       => "sqlite",
    "dbname"       => "nextcloud",
    "dbtableprefix" => "",
];
```

MySQL database

Using the following parameter settings, the “Finish setup” screen requests data directory and admin credentials settings.

```
<?php
$AUTOCONFIG = array(
    "dbtype"       => "mysql",
    "dbname"       => "nextcloud",
    "dbuser"       => "username",
    "dbpass"       => "password",
    "dbhost"       => "localhost",
    "dbtableprefix" => "",
);
```

PostgreSQL database

Using the following parameter settings, the “Finish setup” screen requests data directory and admin credentials settings.

```
<?php
$AUTOCONFIG = array(
    "dbtype"      => "pgsql",
    "dbname"      => "nextcloud",
    "dbuser"      => "username",
    "dbpass"      => "password",
    "dbhost"      => "localhost",
    "dbtableprefix" => "",
);
```

Note: Keep in mind that the automatic configuration does not eliminate the need for creating the database user and database in advance, as described in [Database configuration](#).

All parameters

Using the following parameter settings, because all parameters are already configured in the file, the Nextcloud installation skips the “Finish setup” screen.

```
<?php
$AUTOCONFIG = array(
    "dbtype"      => "mysql",
    "dbname"      => "nextcloud",
    "dbuser"      => "username",
    "dbpass"      => "password",
    "dbhost"      => "localhost",
    "dbtableprefix" => "",
    "adminlogin"  => "root",
    "adminpass"   => "root-password",
    "directory"   => "/www/htdocs/nextcloud/data",
);
```

Note: Keep in mind that the automatic configuration does not eliminate the need for creating the database user and database in advance, as described in [Database configuration](#).

5.15 Theming

With our theming feature you are able to customize the look and feel of your Nextcloud instance according to the corporate design of your organization by replacing Nextcloud logo and color with your own assets.

The theming-app is enabled by default so the section should appear by default in your admin-settings. If not, check in the apps management that this app is enabled.

5.15.1 Modify the appearance of Nextcloud

You can change the following parameters of the look and feel on your instance:

- Name (e.g. ACME Inc. Cloud)
- Web Address (e.g. <https://acme.inc/>)
- Slogan
- Color: The color of header bar, checkboxes and folder icon
- Logo: The logo will appear in the header and on the log in page. Default has 62/34 px.
- Login image: The background image of the login page
- Additional legal links (Legal notice and Privacy policy link)
- Custom header logo and favicon as alternative to auto-generation based on logo

Theming ⁱ

Theming makes it possible to easily customize the look and feel of your instance and supported clients. This will be visible for all users.

Name	Nextcloud
Web link	https://nextcloud.com
Slogan	a safe home for all your data
Color	#0082C9
Logo	⬆
Login image	⬆ 🗑
	
Advanced options	
Legal notice link	https://...
Privacy policy link	https://...
Header logo	⬆
Favicon	⬆

5.15.2 Configure theming through CLI

Theming configuration can also be adjusted through the `occ theming:config` command.

The following values are available to be set through this:

- name, url, imprintUrl, privacyUrl, slogan, color `occ theming:config name "My Example Cloud"`
- background, logo, favicon, logoheader `occ theming:config logo /tmp/mylogo.png`

Note: Images require to be read from a local file on the Nextcloud server

5.15.3 Theming of icons

According to the parameters you have set, Nextcloud will automatically generate favicons and a header logo depending on the current logo and theming color.

This requires the following additional dependencies:

- PHP module `imagick`
- SVG support for `imagick` (e.g. `libmagickcore-6.q16-3-extra` on Debian 9 and Ubuntu 18.04)

Note: In the advanced options of the theming app you are able to set a custom favicon in case you do not want to use the same logo resources you have set above or you do not want to install the mentioned dependencies.

5.15.4 Branded clients

Note: Nextcloud GmbH provides branding services, delivering sync clients (mobile and desktop) which use your corporate identity and are pre-configured to help your users get up and running in no time. If you are interested in our advanced branding & support subscription, [contact our sales team](#).

The theming app supports to change the URLs to the mobile apps (Android & iOS) that is shown when the webinterface is opened on one of those devices. Then there was a header shown, that redirects the user to the app in the app store. By default this redirects to the Nextcloud apps. In some cases it is wanted that this links to branded versions of those apps. In those cases the IDs and URLs can be set via the `occ`-command:

```
occ config:app:set theming AndroidClientUrl --value "https://play.google.com/store/apps/
↳details?id=com.nextcloud.client"
occ config:app:set theming iTunesAppId --value "1125420102"
occ config:app:set theming iOSClientUrl --value "https://itunes.apple.com/us/app/
↳nextcloud/id1125420102?mt=8"
```

5.16 OAuth2

Nextcloud allows connecting external services (for example Moodle) to your Nextcloud. This is done via OAuth2. See [RFC6749](#) for the OAuth2 specification.

Note: Nextcloud does only support confidential clients.

5.16.1 Add an OAuth2 Application

Head over to your Administrator Security Settings. Here you can add a new OAuth2 client.

OAuth 2.0 clients

OAuth 2.0 allows external services to request access to Nextcloud.

Name	Redirection URI	Client Identifier	Secret
Example Application	https://example.acme.inc/admin/oauth2callback.php	mfc2eFLSTKPzRde56H5fX1JGBh5cmNsVAW3yAC0Enkzx8KjnERfBLonyEQ1Qbc34	****  

Add client

Name	Redirection URI	Add
-----------------------------------	--	------------------------------------

Enter the name of your application and provide a redirection url. You should now have a Client Identifier and Secret. Enter those into your OAuth2 client.

Please provide the OAuth2 application the following details:

- Authorization endpoint: <https://cloud.example.org/apps/oauth2/authorize>
- Token endpoint: <https://cloud.example.org/apps/oauth2/api/v1/token>

Note that you must include `index.php` if pretty URL is not configured - i.e. <https://cloud.example.org/index.php/apps/oauth2/api/v1/token>.

5.16.2 The access token

The access token obtained is a so called Bearer token. Which means that for request to the Nextcloud server you will have to send the proper authorization header.

Authorization: Bearer <TOKEN>

Note that apache by default strips this. Make sure you have `mod_headers`, `mod_rewrite` and `mod_env` enabled.

5.16.3 Security considerations

Nextcloud OAuth2 implementation currently does not support scoped access. This means that every token has full access to the complete account including read and write permission to the stored files. It is essential to store the OAuth2 tokens in a safe way!


Without scopes and restrictable access it is not recommended to use a Nextcloud instance as a user authentication service.

APPS MANAGEMENT

Nextcloud apps can enhance, customize or even restrict the features and experience you and your users has with the Nextcloud server. Next to default enabled functions like Files, Activity and Photos there are other apps like Calendar, Contacts, Talk and more which are enhancing the features of your Nextcloud server.

After installing the Nextcloud server, you might want to consider about enabling, disabling or even restricting some apps to groups depending on your and your users' needs.

6.1 Apps



During the Nextcloud server installation, some apps are enabled by default. To see which apps are enabled go to your Apps page.

Those apps are supported and developed by Nextcloud GmbH directly and have an **Featured**-tag. See [Supported apps](#) for a list of supported apps.


Note: Your Nextcloud server needs to be able to communicate with <https://apps.nextcloud.com> to list and download apps. Please make sure to whitelist this target in your firewall or proxy if necessary.

Note: To get access to work-arounds, long-term-support, priority bug fixing and custom consulting for supported apps, contact our [sales team](#).

Note: If you would like to develop your own Nextcloud app, you can find out more information in our [developer manual](#).

All apps must be licensed under AGPLv3+ or any compatible license.

6.2 Managing apps



You will see which apps are enabled, disabled and available. You'll also see additional app bundles and filters, such as Customization, Security and Monitoring for finding more apps quickly.

In the Apps page you can enable or disable applications. Some apps have configurable options on the Apps page, such as **Enable only for specific groups**, but mainly they are enabled or disabled here, and are configured in your Nextcloud settings (admin and/or user-settings) or in the `config.php`.

Click the app name to view a description of the app and any of the app settings in the Application View field. Clicking the **Enable** button will enable the app. If the app is not part of the Nextcloud installation, it will be downloaded from the app store, installed and enabled.

6.3 Using private API

If private API, rather than the public APIs are used in a third-party app, the installation fails, if `'appcodechecker' => true`, is set in `config.php`.

6.4 Using custom app directories

Use the `apps_paths` array in `config.php` to set any custom apps directory locations. The key **path** defines the absolute file system path to the app folder. The key **url** defines the HTTP web path to that folder, starting at the Nextcloud web root. The key **writable** indicates if a user can install apps in that folder.

Note: To ensure that the default `/apps/` folder only contains apps shipped with Nextcloud, follow this example to setup an `/apps2/` folder which will be used to store all other apps.

```
"apps_paths" => [
    [
        "path"      => OC::$SERVERROOT . "/apps",
        "url"       => "/apps",
        "writable"  => false,
    ],
    [
        "path"      => OC::$SERVERROOT . "/apps2",
        "url"       => "/apps2",
        "writable"  => true,
    ],
],
```

Note: Apps paths can be located outside the server root. However, for any **path** outside the server root, you need to create a symlink in the server root that points **url** to **path**. For instance, if **path** is `/var/local/lib/nextcloud/apps`, and **url** is `/apps2`, then you would do this in the server root: `ln -sf /var/local/lib/nextcloud/apps ./apps2`

6.5 Using a self hosted apps store

Enables the installation of apps from a self hosted apps store. Requires that at least one of the configured apps directories is writable.

To enable a self hosted apps store:

1. Set the **appstoreenabled** parameter to “true”.

This parameter is used to enable the apps store in Nextcloud.

2. Set the **appstoreurl** to the URL of your Nextcloud apps store.

This parameter is used to set the http path to your self hosted Nextcloud apps store.

```
"appstoreenabled" => true,
"appstoreurl"     => "https://my.appstore.instance/v1",
```

By default the apps store is enabled and configured to use `https://apps.nextcloud.com/api/v1` as apps store url. Nextcloud will fetch `apps.json` and `categories.json` from there. To use the defaults again remove **appstoreenabled** and **appstoreurl** from the configuration.

Example: If `categories.json` is available at `https://apps.nextcloud.com/api/v1/categories.json` the apps store url is `https://apps.nextcloud.com/api/v1`.

USER MANAGEMENT

7.1 User management


On the User management page of your Nextcloud Web UI you can:

- Create new users
- View all of your users in a single scrolling window
- Filter users by group
- See what groups they belong to
- Edit their full names and passwords
- See their data storage locations
- View and set quotas
- Create and edit their email addresses
- Send an automatic email notification to new users
- Disable and Enable users
- Delete them with a single click


The default view displays basic information about your users.

Username	Password	Groups	Create	Search Users		
Username	Full Name	Password	Groups	Group Admin for	Quota	
 admin	admin	●●●●●●●●	admin ▼	no group ▼	Default ▼	
 layla	layla	●●●●●●●●	users, artists ▼	artists ▼	10 GB ▼	
 molly	molly	●●●●●●●●	users ▼	no group ▼	Default ▼	
 ritasue	ritasue	●●●●●●●●	artists ▼	users ▼	10 GB ▼	
 stashcat	stashcat	●●●●●●●●	users, admin ▼	no group ▼	5 GB ▼	

The Group filters on the left sidebar lets you quickly filter users by their group memberships, and create new groups.



Click the gear icon on the lower left sidebar to set a default storage quota, and to display additional fields: **Show storage location**, **Show last log in**, **Show user backend**, **Send email to new users**, and **Show email address**.



User accounts have the following properties:

Login Name (Username) The unique ID of a Nextcloud user, and it cannot be changed.

Full Name The user's display name that appears on file shares, the Nextcloud Web interface, and emails. Admins and users may change the Full Name anytime. If the Full Name is not set it defaults to the login name.

Password The admin sets the new user's first password. Both the user and the admin can change the user's password at anytime.

Groups You may create groups, and assign group memberships to users. By default new users are not assigned to any groups.

Group Admin Group admins are granted administrative privileges on specific groups, and can add and remove users from their groups.

Quota The maximum disk space assigned to each user. Any user that exceeds the quota cannot upload or sync data. You have the option to include external storage in user quotas.

7.1.1 Creating a new user

To create a user account:

- Enter the new user's **Login Name** and their initial **Password**
- Optionally, assign **Groups** memberships
- Click the **Create** button

	Username	Full name
	terry	
	admin	admin
	john	John Doe

Login names may contain letters (a-z, A-Z), numbers (0-9), dashes (-), underscores (_), periods (.), spaces () and at signs (@). After creating the user, you may fill in their **Full Name** if it is different than the login name, or leave it for the user to complete.

If you have checked **Send email to new user** in the control panel on the lower left sidebar, you may also enter the new user's email address, and Nextcloud will automatically send them a notification with their new login information. You may edit this email using the email template editor on your Admin page (see [Email](#)).

Set the **Send email to new user**-checkbox allows you to leave the **Password** field empty. The user will get an activation-email to set their own password.

7.1.2 Reset a user's password

You cannot recover a user's password, but you can set a new one:

- Hover your cursor over the user's **Password** field
- Click on the **pencil icon**
- Enter the user's new password in the password field, and remember to provide the user with their password

If you have encryption enabled, there are special considerations for user password resets. Please see [Encryption configuration](#).

7.1.3 Renaming a user


Each Nextcloud user has two names: a unique **Login Name** used for authentication, and a **Full Name**, which is their display name. You can edit the display name of a user, but you cannot change the login name of any user.

To set or change a user's display name:

- Hover your cursor over the user's **Full Name** field
- Click on the **Pencil icon**
- Enter the user's new display name

7.1.4 Granting administrator privileges to a user

Nextcloud has two types of administrators: **Super Administrators** and **Group Administrators**. Group administrators have the rights to create, edit and delete users in their assigned groups. Group administrators cannot access system settings, or add or modify users in the groups that they are not **Group Administrators** for. Use the dropdown menus in the **Group Admin** column to assign group admin privileges.



Super Administrators have full rights on your Nextcloud server, and can access and modify all settings. To assign the **Super Administrators** role to a user, simply add them to the **admin** group.

7.1.5 Managing groups

You can assign new users to groups when you create them, and create new groups when you create new users. You may also use the **Add Group** button at the top of the left pane to create new groups. New group members will immediately have access to file shares that belong to their new groups.

7.1.6 Setting Storage quotas

Click the gear on the lower left pane to set a default storage quota. This is automatically applied to new users. You may assign a different quota to any user by selecting from the **Quota** dropdown, selecting either a preset value or entering a custom value. When you create custom quotas, use the normal abbreviations for your storage values such as 500 MB, 5 GB, 5 TB, and so on.

You now have a configurable option in `config.php` that controls whether external storage is counted against user's quotas. This is still experimental, and may not work as expected. The default is to not count external storage as part of user storage quotas. If you prefer to include it, then change the default `false` to `true`.

```
'quota_include_external_storage' => false,
```

Note: If an external storage is defined as root, the quota will not be calculable and will be **ignored**.

Metadata (such as thumbnails, temporary files, and encryption keys) takes up about 10% of disk space, but is not counted against user quotas. Users can check their used and available space on their Personal pages. Only files that originate with users count against their quotas, and not files shared with them that originate from other users. For example, if you upload files to a different user's share, those files count against your quota. If you re-share a file that another user shared with you, that file does not count against your quota, but the originating user's.


Encrypted files are a little larger than unencrypted files; the unencrypted size is calculated against the user's quota.

Deleted files that are still in the trash bin do not count against quotas. The trash bin is set at 50% of quota. Deleted file aging is set at 30 days. When deleted files exceed 50% of quota then the oldest files are removed until the total is below 50%.

When version control is enabled, the older file versions are not counted against quotas.

When a user creates a public share via URL, and allows uploads, any uploaded files count against that user's quota.

7.1.7 Disable and enable users




Sometimes you may want to disable a user without permanently deleting their settings and files. The user can be activated any time again, without data-loss.

Hover your cursor over their name on the **Users** page until the “...”-menu icon appears at the far right. After clicking on it, you will see the **Disable** option.

The user will not longer be able to access their Nextcloud until you enable them again. Keep in mind that the files, which were shared by this user will not longer be accessible.

You will find all disabled users in the **disabled**-section on the left pane. Enabling users is as easy as disabling them. Just click on the “...”-menu, and select **Enable**.

7.1.8 Deleting users



Deleting a user is easy: hover your cursor over their name on the **Users** page until the “...”-menu icon appears at the far right. After clicking on it, you will see the **Delete** option. Clicking on it, deletes a user with all their data immediately.

You'll see an undo button at the top of the page, which remains for some seconds. When the undo button is gone you cannot recover the deleted user.

All of the files owned by the user are deleted as well, including all files they have shared. If you need to preserve the user's files and shares, you must first download them from your Nextcloud Files page, which compresses them into a zip file, or use a sync client to copy them to your local computer. See [File Sharing](#) to learn how to create persistent file shares that survive user deletions.

7.2 Resetting a lost admin password

The normal ways to recover a lost password are:

1. Click the password reset link on the login screen; this appears after a failed login attempt. This works only if you have entered your email address on your Personal page in the Nextcloud Web interface, so that the Nextcloud server can email a reset link to you.
2. Ask another Nextcloud server admin to reset it for you.

If neither of these is an option, then you have a third option, and that is using the `occ` command. See [Using the `occ` command](#) to learn more about using the `occ` command.

```
$ sudo -u www-data php /var/www/nextcloud/occ user:resetpassword admin
Enter a new password:
Confirm the new password:
Successfully reset password for admin
```

If your Nextcloud username is not `admin`, then substitute your Nextcloud username.

7.3 Resetting a user password

The Nextcloud login screen displays a **Wrong password. Reset it?** message after a user enters an incorrect password, and then Nextcloud automatically resets their password. However, if you are using a read-only authentication backend such as LDAP or Active Directory, this will not work. In this case you may specify a custom URL in your `config.php` file to direct your user to a server that can handle an automatic reset:

```
'lost_password_link' => 'https://example.org/link/to/password/reset',
```

7.4 User password policy

A password policy is a set of rules designed to enhance computer security by encouraging users to employ strong passwords and use them properly.

In the security-section of your administrator-settings you can configure

- a minimal length of a password. Default is 8 characters.
- a password history
- a password expiration period
- a lockout policy
- to forbid common passwords like 'password' or 'login'.
- to enforce upper and lower case characters
- to enforce numeric characters
- to enforce special characters like ! or :
- to check the password against the list of breached passwords from haveibeenpwned.com (hashed check via haveibeenpwned.com-API)

Password policy

8	Minimum password length
0	User password history
0	Number of days until user password expires
0	Number of login attempts before the user account is blocked (0 for no limit)
☒ Forbid common passwords	
☐ Enforce upper and lower case characters	
☐ Enforce numeric characters	
☐ Enforce special characters	
☐ Check password against the list of breached passwords from haveibeenpwned.com	

This check creates a hash of the password and sends the first 5 characters of this hash to the haveibeenpwned.com API to retrieve a list of all hashes that start with those. Then it checks on the Nextcloud instance if the password hash is in the result set.

7.5 Two-factor authentication


Two-factor authentication adds an additional layer of security to user accounts. In order to log in on an account with two-factor authentication (2FA) enabled, it is necessary to provide both the login password and another factor. 2FA in Nextcloud is pluggable, meaning that they are not part of the Nextcloud Server component but provided by featured and 3rd-party Nextcloud apps.

Several 2FA apps are already available including **TOTP**, a Telegram/Signal/SMS gateway and **U2F**.

Developers can [build new two-factor provider apps](#).

7.5.1 Enabling two-factor authentication

You can enable 2FA by installing and enabling a 2FA app like TOTP which works with Google Authenticator and compatible apps. The apps are available in the Nextcloud App store so by navigating there and clicking **enable** for the app you want, 2FA will be installed and enabled on your Nextcloud server.



Once 2FA has been enabled, users have to [activate it in their personal settings](#).

7.5.2 Enforcing two-factor authentication

By default 2FA is *optional*, hence users are given the choice whether to enable it for their account. Admins may enforce the use of 2FA.

Enforcement is possible systemwide (all users), for selected groups only and can also be excluded for certain groups.

These settings can be found in the administrator's security settings.

The screenshot shows the Nextcloud Server Administration interface. On the left is a sidebar with navigation links: Personal (Personal info, Security, Accessibility, Sharing), Administration (Overview, Basic settings, Sharing, Security, Theming, Groupware, Workflow). The 'Security' link is highlighted. The main content area is titled 'Add client' and contains the 'Two-Factor Authentication' section. This section includes a checkbox 'Enforce two-factor authentication' which is checked. Below it, there's a 'Limit to groups' section with a text input field containing 'admin'. Further down, there's an 'Excluded groups' text input field. A 'Save changes' button is at the bottom of this section. Below the 2FA section is the 'Server-side encryption' section, which has an unchecked checkbox 'Enable server-side encryption'.

When groups are selected/excluded, they use the following logic to determine if a user has 2FA enforced:

- If no groups are selected, 2FA is enabled for everyone except members of the excluded groups
- If groups are selected, 2FA is enabled for all members of these. If a user is both in a selected *and* excluded group, the selected takes precedence and 2FA is enforced.

Note: Should users lose access to their second factor and backup codes, they won't be able to log into their account anymore. As administrator, you can use the [Two-Factor Admin Support app](#) to generate a one-time code for them to log in and unlock their account. You can find out more about the app in its [documentation](#)

7.6 User authentication with IMAP, SMB, FTP and others

You may configure additional user backends with the External User Backends (user_external) app.

See https://github.com/nextcloud/user_external#readme for an up to date documentation.

7.7 User authentication with LDAP

Nextcloud ships with an LDAP application to allow LDAP users (including Active Directory) to appear in your Nextcloud user listings. These users will authenticate to Nextcloud with their LDAP credentials, so you don't have to create separate Nextcloud user accounts for them. You will manage their Nextcloud group memberships, quotas, and sharing permissions just like any other Nextcloud user.

Note: The PHP LDAP module is required; this is supplied by `php-ldap` on most distributions.

The LDAP application supports:

- LDAP group support
- File sharing with Nextcloud users and groups
- Access via WebDAV and Nextcloud Desktop Client
- Versioning, external Storage and all other Nextcloud features
- Seamless connectivity to Active Directory, with no extra configuration required
- Support for primary groups in Active Directory
- Auto-detection of LDAP attributes such as base DN, email, and the LDAP server port number
- Only read access to your LDAP (edit or delete of users on your LDAP is not supported)
- Optional: Allow users to change their LDAP password from Nextcloud

Note: A non-blocking or correctly configured SELinux setup is needed for the LDAP backend to work. Please refer to the [SELinux configuration](#).

7.7.1 Configuration

First enable the LDAP `user` and `group` backend app on the Apps page in Nextcloud. Then go to your Admin page to configure it.

The LDAP configuration panel has four tabs. A correctly completed first tab (“Server”) is mandatory to access the other tabs. A green indicator lights when the configuration is correct. Hover your cursor over the fields to see some pop-up tooltips.

Server tab

Start with the Server tab. You may configure multiple servers if you have them.

Note: Do not configure any failover LDAP hosts here. See [Advanced settings](#) for instructions instead.

At a minimum you must supply the LDAP server's hostname. If your server requires authentication, enter your credentials on this tab. Nextcloud will then attempt to auto-detect the server's port and base DN. The base DN and port are mandatory, so if Nextcloud cannot detect them you must enter them manually.

Server configuration: Configure one or more LDAP servers. Click the **Delete Configuration** button to remove the active configuration.

Host: The host name or IP address of the LDAP server. It can also be a **ldaps://** URI. If you enter the port number, it speeds up server detection.

Examples:

- *directory.my-company.com*
- *ldaps://directory.my-company.com*
- *directory.my-company.com:9876*

Port: The port on which to connect to the LDAP server. The field is disabled in the beginning of a new configuration. If the LDAP server is running on a standard port, the port will be detected automatically. If you are using a non-standard port, Nextcloud will attempt to detect it. If this fails you must enter the port number manually.

Example:

- 389

User DN: The name as DN of a user who has permissions to do searches in the LDAP directory. Leave it empty for anonymous access. We recommend that you have a special LDAP system user for this.

Example:

- *uid=nextcloudsystemuser,cn=sysusers,dc=my-company,dc=com*

Password: The password for the user given above. Empty for anonymous access.

Base DN: The base DN of LDAP, from where all users and groups can be reached. You may enter multiple base DN's, one per line. (Base DN's for users and groups can be set in the Advanced tab.) This field is mandatory. Nextcloud attempts to determine the Base DN according to the provided User DN or the provided Host, and you must enter it manually if Nextcloud does not detect it.

Example:

- `dc=my-company,dc=com`

Users tab

Use this to control which LDAP users are listed as Nextcloud users on your Nextcloud server. In order to control which LDAP users can login to your Nextcloud server use the **Login Attributes** tab. Those LDAP users who have access but are not listed as users (if there are any) will be hidden users. You may bypass the form fields and enter a raw LDAP filter if you prefer.

Limit Nextcloud access to users meeting these criteria:

Only these object classes:

The most common object classes for users are `organizationalPerson`, `person`, `user`, and `inetOrgPerson`. If you are not sure which object class to select, please consult your directory admin.

Only from these groups:

[Edit LDAP Query](#)

LDAP Filter:

Configuration incorrect ■ [i Help](#)

Only those object classes: Nextcloud will determine the object classes that are typically available for user objects in your LDAP. Nextcloud will automatically select the object class that returns the highest amount of users. You may select multiple object classes.

Only from those groups: If your LDAP server supports the `member-of-overlay` in LDAP filters, you can define that only users from one or more certain groups are allowed to appear in user listings in Nextcloud. By default, no value will be selected. You may select multiple groups.

If your LDAP server does not support the `member-of-overlay` in LDAP filters, the input field is disabled. Please contact your LDAP administrator.

Edit LDAP Query: Clicking on this text toggles the filter mode and you can enter the raw LDAP filter directly. Example:

```
(&(objectClass=inetOrgPerson)(memberOf=cn=nextcloudusers,ou=groups,dc=example,dc=com))
```

x users found: This is an indicator that tells you approximately how many users will be listed in Nextcloud. The number updates automatically after any changes.

Login attributes tab

The settings in the Login Attributes tab determine which LDAP users can log in to your Nextcloud system and which attribute or attributes the provided login name is matched against (e.g. LDAP/AD username, email address). You may select multiple user details. (You may bypass the form fields and enter a raw LDAP filter if you prefer.)

You may override your User Filter settings on the Users tab by using a raw LDAP filter.

LDAP Username: If this value is checked, the login value will be compared to the username in the LDAP directory. The corresponding attribute, usually *uid* or *samaccountname* will be detected automatically by Nextcloud.

LDAP Email Address: If this value is checked, the login value will be compared to an email address in the LDAP directory; specifically, the *mailPrimaryAddress* and *mail* attributes.

Other Attributes: This multi-select box allows you to select other attributes for the comparison. The list is generated automatically from the user object attributes in your LDAP server.

Edit LDAP Query: Clicking on this text toggles the filter mode and you can enter the raw LDAP filter directly.

The `%uid` placeholder is replaced with the login name entered by the user upon login.

Examples:

- only username:

```
(&(objectClass=inetOrgPerson)(memberOf=cn=nextcloudusers,ou=groups,dc=example,dc=com)(uid=%uid)
```

- username or email address:

```
((&(objectClass=inetOrgPerson)(memberOf=cn=nextcloudusers,ou=groups,dc=example,dc=com)(|(uid=%uid)(mail=%uid)))
```

Groups tab

By default, no LDAP groups will be available in Nextcloud. The settings in the Groups tab determine which groups will be available in Nextcloud. You may also elect to enter a raw LDAP filter instead.

The screenshot shows the 'Groups' tab in the Nextcloud administration interface. At the top, there are tabs for 'Server', 'Users', 'Login Attributes', 'Groups' (selected), 'Advanced', and 'Expert'. Below the tabs, a message states: 'Groups meeting these criteria are available in Nextcloud:'. There are two selection criteria: 'Only these object classes:' with a dropdown menu labeled 'Select object classes', and 'Only from these groups:' with a dropdown menu labeled 'Select groups'. Below these is a link that says 'Edit LDAP Query'. Underneath the link is a text input field labeled 'LDAP Filter:'. At the bottom left, there is a button that says 'Verify settings and count groups'. Below this button, there is a red square icon followed by the text 'Configuration incorrect' and a 'Back' button. At the bottom right, there is a link that says 'i Help'.

Only these object classes: Nextcloud will determine the object classes that are typically available for group objects in your LDAP server. Nextcloud will only list object classes that return at least one group object. You can select multiple object classes. A typical object class is “group”, or “posixGroup”.

Only from these groups: Nextcloud will generate a list of available groups found in your LDAP server. Then you select the group or groups that get access to your Nextcloud server.

Edit LDAP Query: Clicking on this text toggles the filter mode and you can enter the raw LDAP filter directly.

Example:

- `objectClass=group`

- `objectClass=posixGroup`

y groups found: This tells you approximately how many groups will be available in Nextcloud. The number updates automatically after any change.

7.7.2 Advanced settings

The LDAP Advanced Setting section contains options that are not needed for a working connection. This provides controls to disable the current configuration, configure replica hosts, and various performance-enhancing options.

The Advanced Settings are structured into three parts:

- Connection Settings
- Directory Settings
- Special Attributes

Connection settings

The screenshot shows the 'Advanced' tab of the Nextcloud LDAP configuration interface. The 'Connection Settings' section is expanded, showing the following options:

- Configuration Active:** ☐
- Backup (Replica) Host:**
- Backup (Replica) Port:**
- Disable Main Server:** ☐
- Turn off SSL certificate validation:** ☐
- Cache Time-To-Live:**

Below the 'Connection Settings' section are two expandable sections:

- Directory Settings** (indicated by a right-pointing triangle)
- Special Attributes** (indicated by a right-pointing triangle)

At the bottom of the 'Advanced' tab are two buttons: **Test Configuration** and **Help** (indicated by an 'i' icon).

Configuration Active: Enables or Disables the current configuration. By default, it is turned off. When Nextcloud makes a successful test connection it is automatically turned on.

Backup (Replica) Host: If you have a backup LDAP server, enter the connection settings here. Nextcloud will then automatically connect to the backup when the main server cannot be reached. The backup server must be a replica of the main server so that the object UUIDs match.

Example:

- *directory2.my-company.com*

Backup (Replica) Port: The connection port of the backup LDAP server. If no port is given, but only a host, then the main port (as specified above) will be used.

Example:

- *389*

Disable Main Server: You can manually override the main server and make Nextcloud only connect to the backup server. This is useful for planned downtimes.

Turn off SSL certificate validation: Turns off SSL certificate checking. Use it for testing only! *Note:* The effect of this setting depends on the PHP system configuration. It does for example not work with the [official Nextcloud container image](<https://github.com/nextcloud/docker>). To disable certificate verification for a particular use, append the following configuration line to your */etc/ldap/ldap.conf*:

```
` TLS_REQCERT ALLOW `
```

Cache Time-To-Live: A cache is introduced to avoid unnecessary LDAP traffic, for example caching usernames so they don't have to be looked up for every page, and speeding up loading of the Users page. Saving the configuration empties the cache. The time is given in seconds.

Note that almost every PHP request requires a new connection to the LDAP server. If you require fresh PHP requests we recommend defining a minimum lifetime of 15s or so, rather than completely eliminating the cache.

Examples:

- ten minutes: *600*
- one hour: *3600*

See the Caching section below for detailed information on how the cache operates.

Directory settings

Server
Users
Login Attributes
Groups
Advanced
Expert

▶ Connection Settings
▼ Directory Settings

User Display Name Field displayname
2nd User Display Name Field
Base User Tree One User Base DN per line
User Search Attributes Optional; one attribute per line
Group Display Name Field cn
Base Group Tree One Group Base DN per line
Group Search Attributes Optional; one attribute per line
Group-Member association uniqueMember ▼
Dynamic Group Member URL
Nested Groups
Paging chunksize 500
Enable LDAP password changes per user (New password is sent as plain text to LDAP)
Default password policy DN

▶ Special Attributes

Test Configuration
i Help

User Display Name Field: The attribute that should be used as display name in Nextcloud.

- Example: *displayName*

2nd User Display Name Field: An optional second attribute displayed in brackets after the display name, for example using the mail attribute displays as Molly Foo (molly@example.com).

Base User Tree: The base DN of LDAP, from where all users can be reached. This must be a complete DN, regardless of what you have entered for your Base DN in the Basic setting. You can specify multiple base trees, one on each line.

- Example:

```
cn=programmers,dc=my-company,dc=com
cn=designers,dc=my-company,dc=com
```

User Search Attributes: These attributes are used when searches for users are performed, for example in the share dialogue. The user display name attribute is the default. You may list multiple attributes, one per line.

If an attribute is not available on a user object, the user will not be listed, and will be unable to login. This also affects the display name attribute. If you override the default you must specify the display name attribute here.

- Example:

```
displayName
mail
```

Group Display Name Field: The attribute that should be used as Nextcloud group name. Nextcloud allows a limited set of characters (a-zA-Z0-9,-_@). Once a group name is assigned it cannot be changed.

- Example: *cn*

Base Group Tree: The base DN of LDAP, from where all groups can be reached. This must be a complete DN, regardless of what you have entered for your Base DN in the Basic setting. You can specify multiple base trees, one in each line.

- Example:

```
cn=barcelona,dc=my-company,dc=com
cn=madrid,dc=my-company,dc=com
```

Group Search Attributes: These attributes are used when a search for groups is done, for example in the share dialogue. By default the group display name attribute as specified above is used. Multiple attributes can be given, one in each line.

If you override the default, the group display name attribute will not be taken into account, unless you specify it as well.

- Example:

```
cn
description
```

Group Member association: The attribute that is used to indicate group memberships, i.e. the attribute used by LDAP groups to refer to their users.

Nextcloud detects the value automatically. You should only change it if you have a very valid reason and know what you are doing.

- Example: *uniquemember*

Nested groups: Enable group member retrieval from sub groups.

To allow user listing and login from nested groups, please see **User listing and login per nested groups** in the section **Troubleshooting, Tips and Tricks**.

Enable LDAP password changes per user: Allow LDAP users to change their password and allow Super Administrators and Group Administrators to change the password of their LDAP users.

To enable this feature, the following requirements have to be met:

- General requirements:
- Access control policies must be configured on the LDAP server to grant permissions for password changes. The User DN as configured in *Server Settings* needs to have write permissions in order to update the user-Password attribute.
- Passwords are sent in plaintext to the LDAP server. Therefore, transport encryption must be used for the communication between Nextcloud and the LDAP server, e.g. employ LDAPS.
- Enabling password hashing on the LDAP server is highly recommended. While Active Directory stores passwords in a one-way format by default, OpenLDAP users could configure the `ppolicy_hash_cleartext` directive of the `ppolicy` overlay that ships with OpenLDAP.
- Additional requirements for Active Directory:
- At least a 128-bit transport encryption must be used for the communication between Nextcloud and the LDAP server.
- Make sure that the `fUserPwdSupport` char of the `dSHeuristics` is configured to employ the `userPassword` attribute as `unicodePwd` alias. While this is set accordingly on AD LDS by default, this is not the case on AD DS.

Default password policy DN: This feature requires OpenLDAP with `ppolicy`. The DN of a default password policy will be used for password expiry handling in the absence of any user specific password policy. Password expiry handling features the following:

- When a LDAP password is about to expire, display a warning message to the user showing the number of days left before it expires. Password expiry warnings are displayed through the notifications app for Nextcloud.
- Prompt LDAP users with expired passwords to reset their password during login, provided that an adequate number of grace logins is still available.

Leave the setting empty to keep password expiry handling disabled.

For the password expiry handling feature to work, LDAP password changes per user must be enabled and the LDAP server must be running OpenLDAP with its `ppolicy` module configured accordingly.

- Example:

cn=default,ou=policies,dc=my-company,dc=com

Special attributes

The screenshot shows the 'Special Attributes' configuration page in the Nextcloud Server Administration interface. The page has a top navigation bar with tabs: Server, Users, Login Attributes, Groups, Advanced, and Expert. The 'Advanced' tab is selected. Below the tabs, there are three expandable sections: 'Connection Settings', 'Directory Settings', and 'Special Attributes'. The 'Special Attributes' section is expanded, showing four input fields: 'Quota Field', 'Quota Default', 'Email Field', and 'User Home Folder Naming Rule'. At the bottom of the 'Special Attributes' section, there are two buttons: 'Test Configuration' and 'Help'.

Quota Field: Nextcloud can read an LDAP attribute and set the user quota according to its value. Specify the attribute here, and it will return human-readable values, e.g. “2 GB”. Any quota set in LDAP overrides quotas set on the Nextcloud user management page.

- Example: *NextcloudQuota*

Quota Default: Override Nextcloud default quota for LDAP users who do not have a quota set in the Quota Field.

- Example: *15 GB*

Email Field: Set the user’s email from their LDAP attribute. Leave it empty for default behavior.

- Example: *mail*

User Home Folder Naming Rule: By default, the Nextcloud server creates the user directory in your Nextcloud data directory and gives it the Nextcloud username, e.g. `/var/www/nextcloud/data/alice`. You may want to override this setting and name it after an LDAP attribute value. The attribute can also return an absolute path, e.g. `/mnt/storage43/alice`. Leave it empty for default behavior.

- Example: *cn*

In new Nextcloud installations the home folder rule is enforced. This means that once you set a home folder naming rule (get a home folder from an LDAP attribute), it must be available for all users. If it isn’t available for a user, then that user will not be able to login. Also, the filesystem will not be set up for that user, so their file shares will not be available to other users.

In migrated Nextcloud installations the old behavior still applies, which is using the Nextcloud username as the home folder when an LDAP attribute is not set. You may change this enforcing the home folder rule with the `occ` command in Nextcloud, like this example on Ubuntu:

```
sudo -u www-data php occ config:app:set user_ldap enforce_home_folder_naming_rule --
↪value=1
```

7.7.3 Expert settings

Server
Users
Login Attributes
Groups
Advanced
Expert

Internal Username

By default the internal username will be created from the UUID attribute. It makes sure that the username is unique and characters do not need to be converted. The internal username has the restriction that only these characters are allowed: [a-zA-Z0-9_@-]. Other characters are replaced with their ASCII correspondence or simply omitted. On collisions a number will be added/increased. The internal username is used to identify a user internally. It is also the default name for the user home folder. It is also a part of remote URLs, for instance for all *DAV services. With this setting, the default behavior can be overridden. To achieve a similar behavior as before ownCloud 5 enter the user display name attribute in the following field. Leave it empty for default behavior. Changes will have effect only on newly mapped (added) LDAP users.

Internal Username

Attribute:

Override UUID detection

By default, the UUID attribute is automatically detected. The UUID attribute is used to doubtlessly identify LDAP users and groups. Also, the internal username will be created based on the UUID, if not specified otherwise above. You can override the setting and pass an attribute of your choice. You must make sure that the attribute of your choice can be fetched for both users and groups and it is unique. Leave it empty for default behavior. Changes will have effect only on newly mapped (added) LDAP users and groups.

UUID Attribute for

Users:

UUID Attribute for

Groups:

Username-LDAP User Mapping

Usernames are used to store and assign (meta) data. In order to precisely identify and recognize users, each LDAP user will have an internal username. This requires a mapping from username to LDAP user. The created username is mapped to the UUID of the LDAP user. Additionally the DN is cached as well to reduce LDAP interaction, but it is not used for identification. If the DN changes, the changes will be found. The internal username is used all over. Clearing the mappings will have leftovers everywhere. Clearing the mappings is not configuration sensitive, it affects all LDAP configurations! Never clear the mappings in a production environment, only in a testing or experimental stage.

[i Help](#)

In the Expert Settings fundamental behavior can be adjusted to your needs. The configuration should be well-tested before starting production use.

Internal Username: The internal username is the identifier in Nextcloud for LDAP users. By default it will be created from the UUID attribute. The UUID attribute ensures that the username is unique, and that characters do not need to be converted. Only these characters are allowed: [a-zA-Z0-9_@-]. Other characters are replaced with their ASCII equivalents, or are simply omitted.

The LDAP backend ensures that there are no duplicate internal usernames in Nextcloud, i.e. that it is checking all other activated user backends (including local Nextcloud users). On collisions a random number (between 1000 and 9999) will be attached to the retrieved value. For example, if “alice” exists, the next username may be “alice_1337”.

The internal username is the default name for the user home folder in Nextcloud. It is also a part of remote URLs, for instance for all *DAV services.

You can override all of this with the Internal Username setting. Leave it empty for default behavior. Changes will affect only newly mapped LDAP users.

When configuring this, be aware that the username in Nextcloud is considered immutable and cannot be changed afterwards. This can cause issues when using an attribute that might change, e.g. the email address of a user that will get changed during name change.

- Example: *uid*

Override UUID detection By default, Nextcloud auto-detects the UUID attribute. The UUID attribute is used to uniquely identify LDAP users and groups. The internal username will be created based on the UUID, if not specified otherwise.

You can override the setting and pass an attribute of your choice. You must make sure that the attribute of your choice can be fetched for both users and groups and it is unique. Leave it empty for default behavior. Changes will have effect only on newly mapped LDAP users and groups. It also will have effect when a user's or group's DN changes and an old UUID was cached, which will result in a new user. Because of this, the setting should be applied before putting Nextcloud in production use and clearing the bindings (see the [User and Group Mapping](#) section below).

- Example: *cn*

Username-LDAP User Mapping Nextcloud uses usernames as keys to store and assign data. In order to precisely identify and recognize users, each LDAP user will have a internal username in Nextcloud. This requires a mapping from Nextcloud username to LDAP user. The created username is mapped to the UUID of the LDAP user. Additionally the DN is cached as well to reduce LDAP interaction, but it is not used for identification. If the DN changes, the change will be detected by Nextcloud by checking the UUID value.

The same is valid for groups.

The internal Nextcloud name is used all over in Nextcloud. Clearing the Mappings will have leftovers everywhere. Never clear the mappings in a production environment, but only in a testing or experimental server.

Warning: Clearing the Mappings is not configuration sensitive, it affects all LDAP configurations!

7.7.4 Testing the configuration

The **Test Configuration** button checks the values as currently given in the input fields. You do not need to save before testing. By clicking on the button, Nextcloud will try to bind to the Nextcloud server using the settings currently given in the input fields. If the binding fails you'll see a yellow banner with the error message "The configuration is invalid. Please have a look at the logs for further details."

When the configuration test reports success, save your settings and check if the users and groups are fetched correctly on the Users page.

7.7.5 Additional configuration options via occ

Few configuration settings can only be set on command line via occ.

Attribute update interval

The LDAP backend will update user information that is used within Nextcloud with the values provided by the LDAP server. For instance these are email, quota or the avatar. This happens on every login, the first detection of a user from LDAP and regularly by a background job.

The interval value determines the time between updates of the values and is used to avoid frequent overhead, including time-expensive write actions to the database.

The interval is described in seconds and it defaults to 86400 equalling a day. It is not a per-configuration option.

The value can be modified by:

```
sudo -u www-data php occ config:app:set user_ldap updateAttributesInterval --value=86400
```

A value of 0 will update it on every of the named occasions.

7.7.6 Nextcloud avatar integration

Nextcloud supports user profile pictures, which are also called avatars. If a user has a photo stored in the *jpegPhoto* or *thumbnailPhoto* attribute on your LDAP server, it will be used as their avatar. In this case the user cannot alter their avatar (on their Personal page) as it must be changed in LDAP. *jpegPhoto* is preferred over *thumbnailPhoto*.

Profile picture



Your avatar is provided by your original account.

If the *jpegPhoto* or *thumbnailPhoto* attribute is not set or empty, then users can upload and manage their avatars on their Nextcloud Personal pages. Avatars managed in Nextcloud are not stored in LDAP.

The *jpegPhoto* or *thumbnailPhoto* attribute is fetched once a day to make sure the current photo from LDAP is used in Nextcloud. LDAP avatars override Nextcloud avatars, and when an LDAP avatar is deleted then the most recent Nextcloud avatar replaces it.

Photos served from LDAP are automatically cropped and resized in Nextcloud. This affects only the presentation, and the original image is not changed.

Use a specific attribute or turn off loading of images

It is possible to turn off the avatar integration or specify a single, different attribute to read the image from. It is expected to contain image data just like *jpegPhoto* or *thumbnailPhoto* do.

The behaviour can be changed using the occ command line tool only. Essentially those options are available:

- The default behaviour as described above should be used

```
occ ldap:set-config "s01" "ldapUserAvatarRule" "default"
```
- User images shall not be fetched from LDAP

```
occ ldap:set-config "s01" "ldapUserAvatarRule" "none"
```
- The image should be read from the attribute “selfiePhoto”

```
occ ldap:set-config "s01" "ldapUserAvatarRule" "data:selfiePhoto"
```

The “s01” refers to the configuration ID as can be retrieved per `occ ldap:show-config`.

7.7.7 Troubleshooting, tips and tricks

SSL certificate verification (LDAPS, TLS)

A common mistake with SSL certificates is that they may not be known to PHP. If you have trouble with certificate validation make sure that

- You have the certificate of the server installed on the Nextcloud server
- The certificate is announced in the system’s LDAP configuration file (usually */etc/ldap/ldap.conf*)
- Using LDAPS, also make sure that the port is correctly configured (by default 636)

Microsoft Active Directory

Compared to earlier Nextcloud versions, no further tweaks need to be done to make Nextcloud work with Active Directory. Nextcloud will automatically find the correct configuration in the set-up process.

memberOf / read memberof permissions

If you want to use `memberOf` within your filter you might need to give your querying user the permissions to use it. For Microsoft Active Directory this is described [here](#).

User listing and login per nested groups

When it is intended to allow user listing and login based on a specific group having subgroups (“nested groups”), checking **Nested groups** on **Directory Settings** is not enough. Also the User (and Login) filter need to be changed, by specifying the `LDAP_MATCHING_RULE_IN_CHAIN` matching rule. Change the filter parts containing the *memberof* condition according to this example:

- `(memberof=cn=Nextcloud Users Group,ou=Groups,...)`

to

- `(memberof:1.2.840.113556.1.4.1941:=cn=Nextcloud Users Group,ou=Groups,...)`

Duplicating server configurations

In case you have a working configuration and want to create a similar one or “snapshot” configurations before modifying them you can do the following:

1. Go to the **Server** tab
2. On **Server Configuration** choose *Add Server Configuration*
3. Answer the question *Take over settings from recent server configuration?* with *yes*.
4. (optional) Switch to **Advanced** tab and uncheck **Configuration Active** in the *Connection Settings*, so the new configuration is not used on Save
5. Click on **Save**

Now you can modify and enable the configuration.

7.7.8 Nextcloud LDAP internals

Some parts of how the LDAP backend works are described here.

User and group mapping

In Nextcloud the user or group name is used to have all relevant information in the database assigned. To work reliably a permanent internal user name and group name is created and mapped to the LDAP DN and UUID. If the DN changes in LDAP it will be detected, and there will be no conflicts.

Those mappings are done in the database table `ldap_user_mapping` and `ldap_group_mapping`. The user name is also used for the user’s folder (except if something else is specified in *User Home Folder Naming Rule*), which contains files and meta data.

The internal user name and a visible display name are separated. This is not the case for group names, yet, i.e. a group name cannot be altered.

That means that your LDAP configuration should be good and ready before putting it into production. The mapping tables are filled early, but as long as you are testing, you can empty the tables any time. Do not do this in production.

The attributes of users are fetched on demand (i.e. for sharing autocompletion or in the user management) and then stored inside the Nextcloud database to allow a better performance on our side. They are typically checked twice a day in batches from all users again. Beside that they are also refreshed during a login for this user or can be fetched manually via the occ command `occ ldap:check-user --update USERID` where USERID is Nextcloud’s user id.

Caching

The LDAP information is cached in Nextcloud memory cache, and you must install and configure the memory cache (see [Memory caching](#)). The Nextcloud **Cache** helps to speed up user interactions and sharing. It is populated on demand, and remains populated until the **Cache Time-To-Live** for each unique request expires. User logins are not cached, so if you need to improve login times set up a slave LDAP server to share the load.

You can adjust the **Cache Time-To-Live** value to balance performance and freshness of LDAP data. All LDAP requests will be cached for 10 minutes by default, and you can alter this with the **Cache Time-To-Live** setting. The cache answers each request that is identical to a previous request, within the time-to-live of the original request, rather than hitting the LDAP server.

The **Cache Time-To-Live** is related to each single request. After a cache entry expires there is no automatic trigger for re-populating the information, as the cache is populated only by new requests, for example by opening the User administration page, or searching in a sharing dialog.

There is one trigger which is automatically triggered by a certain background job which keeps the `user-group-mappings` up-to-date, and always in cache.

Under normal circumstances, all users are never loaded at the same time. Typically the loading of users happens while page results are generated, in steps of 30 until the limit is reached or no results are left. For this to work on a Nextcloud-Server and LDAP-Server, **Paged Results** must be supported.

Nextcloud remembers which user belongs to which LDAP-configuration. That means each request will always be directed to the right server unless a user is defunct, for example due to a server migration or unreachable server. In this case the other servers will also receive the request.

Handling with backup server

When Nextcloud is not able to contact the main LDAP server, Nextcloud assumes it is offline and will not try to connect again for the time specified in **Cache Time-To-Live**. If you have a backup server configured Nextcloud will connect to it instead. When you have scheduled downtime, check **Disable Main Server** to avoid unnecessary connection attempts.

7.7.9 Note

When a LDAP object's name or surname, that is display name attribute, by default "displayname", is left empty, Nextcloud will treat it as an empty object, therefore no results from this user or AD-Object will be shown to avoid gathering of technical accounts.

7.8 LDAP user cleanup

LDAP User Cleanup is a new feature in the LDAP user and group backend application. LDAP User Cleanup is a background process that automatically searches the Nextcloud LDAP mappings table, and verifies if the LDAP users are still available. Any users that are not available are marked as `deleted` in the `oc_preferences` database table. Then you can run a command to display this table, displaying only the users marked as `deleted`, and then you have the option of removing their data from your Nextcloud data directory.

These items are removed upon cleanup:

- Local Nextcloud group assignments
- User preferences (DB table `oc_preferences`)
- User's Nextcloud home folder
- User's corresponding entry in `oc_storages`

There are two prerequisites for LDAP User Cleanup to operate:

1. Set `ldapUserCleanupInterval` in `config.php` to your desired check interval in minutes. The default is 51 minutes.
2. All configured LDAP connections are enabled and operating correctly. As users can exist on multiple LDAP servers, you want to be sure that all of your LDAP servers are available so that a user on a temporarily disconnected LDAP server is not marked as `deleted`.

The background process examines 50 users at a time, and runs at the interval you configured with `ldapUserCleanupInterval`. For example, if you have 200 LDAP users and your `ldapUserCleanupInterval` is 20 minutes, the process will examine the first 50 users, then 20 minutes later the next 50 users, and 20 minutes later the next 50, and so on.

The amount of users to check can be set to a custom value via `occ` command. The following example sets it to 300:

```
sudo -u www-data php occ config:app:set --value=300 user_ldap cleanUpJobChunkSize
```

There are two occ commands to use for examining a table of users marked as deleted, and then manually deleting them. The occ command is in your Nextcloud directory, for example `/var/www/nextcloud/occ`, and it must be run as your HTTP user. To learn more about occ, see [Using the occ command](#).

These examples are for Ubuntu Linux:

1. `sudo -u www-data php occ ldap:show-remnants` displays a table with all users that have been marked as deleted, and their LDAP data.
2. `sudo -u www-data php occ user:delete [user]` removes the user's data from the Nextcloud data directory.

This example shows what the table of users marked as deleted looks like:

```
$ sudo -u www-data php occ ldap:show-remnants
+-----+-----+-----+-----+
↪-----+
| Nextcloud name | Display Name | LDAP UID | LDAP DN |
↪      |
+-----+-----+-----+-----+
↪-----+
| aaliyah_brown  | aaliyah brown | aaliyah_brown | uid=aaliyah_brown,ou=people,
↪dc=com |
| aaliyah_hammes | aaliyah hammes | aaliyah_hammes | uid=aaliyah_hammes,ou=people,
↪dc=com |
| aaliyah_johnston| aaliyah johnston| aaliyah_johnston | uid=aaliyah_johnston,ou=people,
↪dc=com|
| aaliyah_kunze   | aaliyah kunze   | aaliyah_kunze   | uid=aaliyah_kunze,ou=people,
↪dc=com |
+-----+-----+-----+-----+
↪-----+
```

Following flags can be specified additionally:

`--short-date`: formats the dates for `Last login` and `Detected on` in a short Y-m-d format (e.g. 2019-01-14)

`--json-`: instead of a table, the output is json-encoded. This makes it easy to process the data programmatically.

Then you can run `sudo -u www-data php occ user:delete aaliyah_brown` to delete user `aaliyah_brown`. You must use the user's Nextcloud name.

7.8.1 Deleting local Nextcloud users

You may also use `occ user:delete [user]` to remove a local Nextcloud user; this removes their user account and their data.

7.9 The LDAP configuration API

All methods require that the “OCS-APIREQUEST” header be set to “true”. Methods take an optional “format” parameter, which may be “xml” (the default) or “json”.

7.9.1 Creating a configuration

Creates a new and empty LDAP configuration. It returns its ID. Authentication is done by sending a basic HTTP authentication header.

Syntax: `ocs/v2.php/apps/user_ldap/api/v1/config`

- HTTP method: POST

Example

```
$ curl -X POST https://admin:secret@example.com/ocs/v2.php/apps/user_ldap/api/v1/config -H "OCS-APIREQUEST: true"
```

- Creates a new, empty configuration

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <status>ok</status>
    <statuscode>200</statuscode>
    <message>OK</message>
  </meta>
  <data>
    <configID>s01</configID>
  </data>
</ocs>
```

7.9.2 Deleting a configuration

Deletes a given LDAP configuration. Authentication is done by sending a basic HTTP authentication header.

Syntax: `ocs/v2.php/apps/user_ldap/api/v1/config/{configID}`

- HTTP method: DELETE

Example

```
$ curl -X DELETE ``https://admin:secret@example.com/ocs/v2.php/apps/user_ldap/api/v1/
↪config/s02 -H "OCS-APIREQUEST: true"
```

- deletes the LDAP configuration

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <status>ok</status>
    <statuscode>200</statuscode>
    <message>OK</message>
  </meta>
  <data/>
</ocs>
```

7.9.3 Reading a configuration

Returns all keys and values of the specified LDAP configuration. Authentication is done by sending a basic HTTP authentication header.

Syntax: `ocs/v2.php/apps/user_ldap/api/v1/config/{configID}`

- HTTP method: GET
- url argument: `showPassword` - int, optional, default 0, whether to return the password in clear text

Example

```
$ curl -X GET https://admin:secret@example.com/ocs/v2.php/apps/user_ldap/api/v1/config/
↪s02?showPassword=1 -H "OCS-APIREQUEST: true"
```

- fetches the LDAP configuration

XML output

```

<?xml version="1.0"?>
<ocs>
  <meta>
    <status>ok</status>
    <statuscode>200</statuscode>
    <message>OK</message>
  </meta>
  <data>
    <ldapHost>ldap://ldap.server.tld</ldapHost>
    <ldapPort>389</ldapPort>
    <ldapBackupHost></ldapBackupHost>
    <ldapBackupPort></ldapBackupPort>
    <ldapBase>ou=Department XLII,dc=example,dc=com</ldapBase>
    <ldapBaseUsers>ou=users,ou=Department XLII,dc=example,dc=com</ldapBaseUsers>
    <ldapBaseGroups>ou=Department XLII,dc=example,dc=com</ldapBaseGroups>
    <ldapAgentName>cn=root,dc=example,dc=com</ldapAgentName>
    <ldapAgentPassword>Secret</ldapAgentPassword>
    <ldapTLS>1</ldapTLS>
    <turnOffCertCheck>0</turnOffCertCheck>
    <ldapIgnoreNamingRules/>
    <ldapUserDisplayName>displayname</ldapUserDisplayName>
    <ldapUserDisplayName2>uid</ldapUserDisplayName2>
    <ldapGidNumber>gidNumber</ldapGidNumber>
    <ldapUserFilterObjectclass>inetOrgPerson</ldapUserFilterObjectclass>
    <ldapUserFilterGroups></ldapUserFilterGroups>
    <ldapUserFilter>(& (objectclass=nextcloudUser) (nextcloudEnabled=TRUE))</
    ldapUserFilter>
    <ldapUserFilterMode>1</ldapUserFilterMode>
    <ldapGroupFilter>(& (|(objectclass=nextcloudGroup)))</ldapGroupFilter>
    <ldapGroupFilterMode>0</ldapGroupFilterMode>
    <ldapGroupFilterObjectclass>nextcloudGroup</ldapGroupFilterObjectclass>
    <ldapGroupFilterGroups></ldapGroupFilterGroups>
    <ldapGroupMemberAssocAttr>memberUid</ldapGroupMemberAssocAttr>
    <ldapGroupDisplayName>cn</ldapGroupDisplayName>
    <ldapLoginFilter>(& (|(objectclass=inetOrgPerson)) (uid=%uid))</ldapLoginFilter>
    <ldapLoginFilterMode>0</ldapLoginFilterMode>
    <ldapLoginFilterEmail>0</ldapLoginFilterEmail>
    <ldapLoginFilterUsername>1</ldapLoginFilterUsername>
    <ldapLoginFilterAttributes></ldapLoginFilterAttributes>
    <ldapQuotaAttribute></ldapQuotaAttribute>
    <ldapQuotaDefault>20 MB</ldapQuotaDefault>
    <ldapEmailAttribute>mail</ldapEmailAttribute>
    <ldapCacheTTL>600</ldapCacheTTL>
    <ldapUidUserAttribute>auto</ldapUidUserAttribute>
    <ldapUidGroupAttribute>auto</ldapUidGroupAttribute>
    <ldapOverrideMainServer></ldapOverrideMainServer>
    <ldapConfigurationActive>1</ldapConfigurationActive>
    <ldapAttributesForUserSearch>uid;sn;givenname</ldapAttributesForUserSearch>
    <ldapAttributesForGroupSearch></ldapAttributesForGroupSearch>
    <ldapExperiencedAdmin>0</ldapExperiencedAdmin>
    <homeFolderNamingRule>attr:mail</homeFolderNamingRule>
  </data>
</ocs>

```

(continues on next page)

(continued from previous page)

```

<hasPagedResultSupport></hasPagedResultSupport>
<hasMemberOfFilterSupport>1</hasMemberOfFilterSupport>
<useMemberOfToDetectMembership>1</useMemberOfToDetectMembership>
<ldapExpertUsernameAttr></ldapExpertUsernameAttr>
<ldapExpertUUIDUserAttr></ldapExpertUUIDUserAttr>
<ldapExpertUUIDGroupAttr></ldapExpertUUIDGroupAttr>
<lastJpegPhotoLookup>0</lastJpegPhotoLookup>
<ldapNestedGroups>0</ldapNestedGroups>
<ldapPagingSize>500</ldapPagingSize>
<turnOnPasswordChange>1</turnOnPasswordChange>
<ldapDynamicGroupMemberURL></ldapDynamicGroupMemberURL>
<ldapDefaultPPolicyDN></ldapDefaultPPolicyDN>
</data>
</ocs>

```

7.9.4 Modifying a configuration

Updates a configuration with the provided values. Authentication is done by sending a basic HTTP authentication header.

Syntax: `ocs/v2.php/apps/user_ldap/api/v1/config/{configID}`

- HTTP method: PUT
- url argument: configData - array, see table below for the fields. All fields are optional. The values must be url-encoded.

Example

```

$ curl -X PUT https://admin:secret@example.com/ocs/v2.php/apps/user_ldap/api/v1/config/
s01 -H "OCS-APIREQUEST: true" -d "configData[ldapHost]=ldap%3A%2F%2Fldap.server.tld &
configData[ldapPort]=389"

```

- updates the LDAP configuration

XML output

```

<?xml version="1.0"?>
<ocs>
  <meta>
    <status>ok</status>
    <statusCode>200</statusCode>
    <message>OK</message>
  </meta>
  <data/>
</ocs>

```

7.9.5 Configuration keys

Key	Mode	Required	Description
ldapHost	rw	yes	LDAP server host, supports protocol
ldapPort	rw	yes	LDAP server port
ldapBackupHost	rw	no	LDAP replica host
ldapBackupPort	rw	no	LDAP replica port
ldapOverrideMainServer	rw	no	Whether replica should be used instead
ldapBase	rw	yes	Base
ldapBaseUsers	rw	no	Base for users, defaults to general base if not specified
ldapBaseGroups	rw	no	Base for groups, defaults to general base if not specified
ldapAgentName	rw	no	DN for the (service) user to connect to LDAP
ldapAgentPassword	rw	no	Password for the service user
ldapTLS	rw	no	Whether to use StartTLS
turnOffCertCheck	rw	no	Turns off certificate validation for TLS connections
ldapIgnoreNamingRules	rw	no	Backwards compatibility, do not set it.
ldapUserDisplayName	rw	yes	Attribute used as display name for users
ldapUserDisplayName2	rw	no	Additional attribute, if set show on brackets next to the main attribute
ldapUserAvatarRule	rw	no	Specify the avatar integration behavior, possible values: “default”, “none”
ldapGidNumber	rw	no	group ID attribute, needed for primary groups on OpenLDAP (and comp)
ldapUserFilterObjectclass	rw	no	set by the Settings Wizard (web UI)
ldapUserFilterGroups	rw	no	set by the Settings Wizard (web UI)
ldapUserFilter	rw	yes	LDAP Filter used to retrieve user
ldapUserFilterMode	rw	no	used by the Settings Wizard, set to 1 for manual editing
ldapAttributesForUserSearch	rw	no	attributes to be matched when searching for users. separate by ;
ldapGroupFilter	rw	no	LDAP Filter used to retrieve groups
ldapGroupFilterMode	rw	no	used by the Settings Wizard, set to 1 for manual editing
ldapGroupFilterObjectclass	rw	no	set by the Settings Wizard (web UI)
ldapGroupFilterGroups	rw	no	set by the Settings Wizard (web UI)
ldapGroupMemberAssocAttr	rw	no	attribute that indicates group members, one of: member, memberUid, ur
ldapGroupDisplayName	rw	no	Attribute used as display name for groups, required if groups are used
ldapAttributesForGroupSearch	rw	no	attributes to be matched when searching for groups. separate by ;
ldapLoginFilter	rw	yes	LDAP Filter used to authenticate users
ldapLoginFilterMode	rw	no	used by the Settings Wizard, set to 1 for manual editing
ldapLoginFilterEmail	rw	no	set by the Settings Wizard (web UI)
ldapLoginFilterUsername	rw	no	set by the Settings Wizard (web UI)
ldapLoginFilterAttributes	rw	no	set by the Settings Wizard (web UI)
ldapQuotaAttribute	rw	no	LDAP attribute containing the quota value (per user)
ldapQuotaDefault	rw	no	Default Quota, if specified quota attribute is empty
ldapEmailAttribute	rw	no	LDAP attribute containing the email address (takes first if multiple are s
ldapCacheTTL	rw	no	How long results from LDAP are cached, defaults to 10min
ldapUuidUserAttribute	r	no	set in runtime
ldapUuidGroupAttribute	r	no	set in runtime
ldapConfigurationActive	rw	no	whether this configuration is active. 1 is on, 0 is off.
ldapExperiencedAdmin	rw	no	used by the Settings Wizard, set to 1 for manual editing
homeFolderNamingRule	rw	no	LDAP attribute to use a user folder name
hasPagedResultSupport	r	no	set in runtime
hasMemberOfFilterSupport	r	no	set in runtime
useMemberOfToDetectMembership	rw	no	Whether to use memberOf to detect group memberships
ldapExpertUsernameAttr	rw	no	LDAP attribute to use as internal username. Might be modified (e.g. to a

Table 1 – continued from previous page

Key	Mode	Required	Description
ldapExpertUUIDUserAttr	rw	no	override the LDAP servers UUID attribute to identify LDAP user record
ldapExpertUUIDGroupAttr	rw	no	override the LDAP servers UUID attribute to identify LDAP group record
lastJpegPhotoLookup	r	no	set in runtime
ldapNestedGroups	rw	no	Whether LDAP supports nested groups
ldapPagingSize	rw	no	Number of results to return per page
turnOnPasswordChange	rw	no	Whether users are allowed to change passwords (hashing must happen on server)
ldapDynamicGroupMemberURL	rw	no	URL for dynamic groups
ldapDefaultPPolicyDN	rw	no	PPolicy DN for password rules

7.10 User provisioning API

The Provisioning API application enables a set of APIs that external systems can use to create, edit, delete and query user attributes, query, set and remove groups, set quota and query total storage used in Nextcloud. Group admin users can also query Nextcloud and perform the same functions as an admin for groups they manage. The API also enables an admin to query for active Nextcloud applications, application info, and to enable or disable an app remotely. HTTP requests can be used via a Basic Auth header to perform any of the functions listed above. The Provisioning API app is enabled by default.

The base URL for all calls to the share API is `https://cloud.example.com/ocs/v1.php/cloud`.

All calls to OCS endpoints require the `OCS-APIRequest` header to be set to `true`.

All POST requests require the `Content-Type: application/x-www-form-urlencoded` header. (Note: Some libraries like cURL set this header automatically, others require setting the header explicitly.)

7.10.1 Instruction set for users

Add a new user

Create a new user on the Nextcloud server. Authentication is done by sending a basic HTTP authentication header.

Syntax: `ocs/v1.php/cloud/users`

- HTTP method: POST
- POST argument: `userid` - string, the required username for the new user
- POST argument: `password` - string, the password for the new user, leave empty to send welcome mail
- POST argument: `displayName` - string, the display name for the new user
- POST argument: `email` - string, the email for the new user, required if password empty
- POST argument: `groups` - array, the groups for the new user
- POST argument: `subadmin` - array, the groups in which the new user is subadmin
- POST argument: `quota` - string, quota for the new user
- POST argument: `language` - string, language for the new user

Status codes:

- 100 - successful
- 101 - invalid input data

- 102 - username already exists
- 103 - unknown error occurred whilst adding the user
- 104 - group does not exist
- 105 - insufficient privileges for group
- 106 - no group specified (required for subadmins)
- 107 - all errors that contain a hint - for example “Password is among the 1,000,000 most common ones. Please make it unique.” (this code was added in 12.0.6 & 13.0.1)
- 108 - password and email empty. Must set password or an email
- 109 - invitation email cannot be send

Example

```
$ curl -X POST http://admin:secret@example.com/ocs/v1.php/cloud/users -d userid="Frank" -  
↪d password="frankspassword"
```

- Creates the user Frank with password frankspassword
- optionally groups can be specified by one or more groups[] query parameters: URL -d groups[]="admin" -D groups[]="Team1"

XML output

```
<?xml version="1.0"?>  
<ocs>  
  <meta>  
    <status>ok</status>  
    <statuscode>100</statuscode>  
    <message/>  
  </meta>  
  <data/>  
</ocs>
```

Search/get users

Retrieves a list of users from the Nextcloud server. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: ocs/v1.php/cloud/users

- HTTP method: GET
- url arguments: search - string, optional search string
- url arguments: limit - int, optional limit value
- url arguments: offset - int, optional offset value

Status codes:

- 100 - successful

Example

```
$ curl -X GET http://admin:secret@example.com/ocs/v1.php/cloud/users?search=Frank
```

- Returns list of users matching the search string.

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
  <data>
    <users>
      <element>Frank</element>
    </users>
  </data>
</ocs>
```

Get data of a single user

Retrieves information about a single user. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/users/{userid}`

- HTTP method: GET

Status codes:

- 100 - successful

Example

```
$ curl -X GET http://admin:secret@example.com/ocs/v1.php/cloud/users/Frank
```

- Returns information on the user Frank

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
  <data>
    <enabled>true</enabled>
  </data>
</ocs>
```

(continues on next page)

(continued from previous page)

```
<id>Frank</id>
<quota>0</quota>
<email>frank@example.org</email>
<displayname>Frank K.</displayname>
<phone>0123 / 456 789</phone>
<address>Foobar 12, 12345 Town</address>
<website>https://nextcloud.com</website>
<twitter>Nextcloud</twitter>
<groups>
  <element>group1</element>
  <element>group2</element>
</groups>
</data>
</ocs>
```

Edit data of a single user

Edits attributes related to a user. Users are able to edit email, displayname and password; admins can also edit the quota value. Further restrictions may apply, check the *List of editable data fields* endpoint. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/users/{userid}`

- HTTP method: PUT
- PUT argument: key, the field to edit:
 - email
 - quota
 - displayname
 - display (**deprecated** use *displayname* instead)
 - phone
 - address
 - website
 - twitter
 - password
- PUT argument: value, the new value for the field

Status codes:

- 100 - successful
- 101 - user not found
- 102 - invalid input data

Examples

```
$ curl -X PUT http://admin:secret@example.com/ocs/v1.php/cloud/users/Frank -d key="email"  
↪ -d value="franksnewemail@example.org"
```

- Updates the email address for the user Frank

```
$ curl -X PUT http://admin:secret@example.com/ocs/v1.php/cloud/users/Frank -d key="quota"  
↪ -d value="100MB"
```

- Updates the quota for the user Frank

XML output

```
<?xml version="1.0"?>  
<ocs>  
  <meta>  
    <statusCode>100</statusCode>  
    <status>ok</status>  
  </meta>  
  <data/>  
</ocs>
```

List of editable data fields

Edits attributes related to a user. Users are able to edit email, displayname and password; admins can also edit the quota value. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: ocs/v1.php/cloud/user/fields

- HTTP method: GET

Status codes:

- 100 - successful

Examples

```
$ curl -X GET http://admin:secret@example.com/ocs/v1.php/cloud/user/fields
```

- Gets the list of fields

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <status>ok</status>
    <statuscode>100</statuscode>
    <message>OK</message>
  </meta>
  <data>
    <element>displayname</element>
    <element>email</element>
    <element>phone</element>
    <element>address</element>
    <element>website</element>
    <element>twitter</element>
  </data>
</ocs>
```

Disable a user

Disables a user on the Nextcloud server so that the user cannot login anymore. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/users/{userid}/disable`

- HTTP method: PUT

Statuscodes:

- 100 - successful
- 101 - failure

Example

```
$ curl -X PUT http://admin:secret@example.com/ocs/v1.php/cloud/users/Frank/disable
```

- Disables the user Frank

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <status>ok</status>
    <statuscode>100</statuscode>
    <message/>
  </meta>
  <data/>
</ocs>
```

Enable a user

Enables a user on the Nextcloud server so that the user can login again. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/users/{userid}/enable`

- HTTP method: PUT

Statuscodes:

- 100 - successful
- 101 - failure

Example

```
$ curl -X PUT http://admin:secret@example.com/ocs/v1.php/cloud/users/Frank/enable
```

- Enables the user Frank

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <status>ok</status>
    <statuscode>100</statuscode>
    <message/>
  </meta>
  <data/>
</ocs>
```

Delete a user

Deletes a user from the Nextcloud server. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/users/{userid}`

- HTTP method: DELETE

Statuscodes:

- 100 - successful
- 101 - failure

Example

```
$ curl -X DELETE http://admin:secret@example.com/ocs/v1.php/cloud/users/Frank
```

- Deletes the user Frank

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
  <data/>
</ocs>
```

Get user's groups

Retrieves a list of groups the specified user is a member of. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/users/{userid}/groups`

- HTTP method: GET

Status codes:

- 100 - successful

Example

```
$ curl -X GET http://admin:secret@example.com/ocs/v1.php/cloud/users/Frank/groups
```

- Retrieves a list of groups of which Frank is a member

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
  <data>
    <groups>
      <element>admin</element>
      <element>group1</element>
    </groups>
  </data>
</ocs>
```

(continues on next page)

(continued from previous page)

```
</data>
</ocs>
```

Add user to group

Adds the specified user to the specified group. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/users/{userid}/groups`

- HTTP method: POST
- POST argument: groupid, string - the group to add the user to

Status codes:

- 100 - successful
- 101 - no group specified
- 102 - group does not exist
- 103 - user does not exist
- 104 - insufficient privileges
- 105 - failed to add user to group

Example

```
$ curl -X POST http://admin:secret@example.com/ocs/v1.php/cloud/users/Frank/groups -d
↪groupid="newgroup"
```

- Adds the user Frank to the group newgroup

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
  <data/>
</ocs>
```

Remove user from group

Removes the specified user from the specified group. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/users/{userid}/groups`

- HTTP method: DELETE
- DELETE argument: groupid, string - the group to remove the user from

Status codes:

- 100 - successful
- 101 - no group specified
- 102 - group does not exist
- 103 - user does not exist
- 104 - insufficient privileges
- 105 - failed to remove user from group

Example

```
$ curl -X DELETE http://admin:secret@example.com/ocs/v1.php/cloud/users/Frank/groups -d ␣  
↪groupid="newgroup"
```

- Removes the user Frank from the group newgroup

XML output

```
<?xml version="1.0"?>  
<ocs>  
  <meta>  
    <statusCode>100</statusCode>  
    <status>ok</status>  
  </meta>  
  <data/>  
</ocs>
```

Promote user to subadmin

Makes a user the subadmin of a group. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/users/{userid}/subadmins`

- HTTP method: POST
- POST argument: groupid, string - the group of which to make the user a subadmin

Status codes:

- 100 - successful
- 101 - user does not exist

- 102 - group does not exist
- 103 - unknown failure

Example

```
$ curl -X POST https://admin:secret@example.com/ocs/v1.php/cloud/users/Frank/subadmins -
  ↪d groupid="group"
```

- Makes the user Frank a subadmin of the group group

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
  <data/>
</ocs>
```

Demote user from subadmin

Removes the subadmin rights for the user specified from the group specified. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/users/{userid}/subadmins`

- HTTP method: DELETE
- DELETE argument: groupid, string - the group from which to remove the user's subadmin rights

Status codes:

- 100 - successful
- 101 - user does not exist
- 102 - user is not a subadmin of the group / group does not exist
- 103 - unknown failure

Example

```
$ curl -X DELETE https://admin:secret@example.com/ocs/v1.php/cloud/users/Frank/subadmins ↪
  ↪d groupid="oldgroup"
```

- Removes Frank's subadmin rights from the oldgroup group

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
  <data/>
</ocs>
```

Get user's subadmin groups

Returns the groups in which the user is a subadmin. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: ocs/v1.php/cloud/users/{userid}/subadmins

- HTTP method: GET

Status codes:

- 100 - successful
- 101 - user does not exist
- 102 - unknown failure

Example

```
$ curl -X GET https://admin:secret@example.com/ocs/v1.php/cloud/users/Frank/subadmins
```

- Returns the groups of which Frank is a subadmin

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <status>ok</status>
    <statuscode>100</statuscode>
    <message/>
  </meta>
  <data>
    <element>testgroup</element>
  </data>
</ocs>
```

Resend the welcome email

The request to this endpoint triggers the welcome email for this user again.

Syntax: `ocs/v1.php/cloud/users/{userid}/welcome`

- HTTP method: POST

Status codes:

- 100 - successful
- 101 - email address not available
- 102 - sending email failed

Example

```
$ curl -X POST https://admin:secret@example.com/ocs/v1.php/cloud/users/Frank/welcome
```

- Sends the welcome email to Frank

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <status>ok</status>
    <statuscode>100</statuscode>
    <message/>
  </meta>
  <data/>
</ocs>
```

7.10.2 Instruction set for groups

Search/get groups

Retrieves a list of groups from the Nextcloud server. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/groups`

- HTTP method: GET
- url arguments: search - string, optional search string
- url arguments: limit - int, optional limit value
- url arguments: offset - int, optional offset value

Status codes:

- 100 - successful

Example

```
$ curl -X GET http://admin:secret@example.com/ocs/v1.php/cloud/groups?search=adm
```

- Returns list of groups matching the search string.

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
  <data>
    <groups>
      <element>admin</element>
    </groups>
  </data>
</ocs>
```

Create a group

Adds a new group. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/groups`

- HTTP method: POST
- POST argument: `groupid`, string - the new groups name

Status codes:

- 100 - successful
- 101 - invalid input data
- 102 - group already exists
- 103 - failed to add the group

Example

```
$ curl -X POST http://admin:secret@example.com/ocs/v1.php/cloud/groups -d groupid=
↪ "newgroup"
```

- Adds a new group called `newgroup`

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
  <data/>
</ocs>
```

Get members of a group

Retrieves a list of group members. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: ocs/v1.php/cloud/groups/{groupid}

- HTTP method: GET

Status codes:

- 100 - successful

Example

```
$ curl -X GET http://admin:secret@example.com/ocs/v1.php/cloud/groups/admin
```

- Returns a list of users in the admin group

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
  <data>
    <users>
      <element>Frank</element>
    </users>
  </data>
</ocs>
```

Get subadmins of a group

Returns subadmins of the group. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/groups/{groupid}/subadmins`

- HTTP method: GET

Status codes:

- 100 - successful
- 101 - group does not exist
- 102 - unknown failure

Example

```
$ curl -X GET https://admin:secret@example.com/ocs/v1.php/cloud/groups/mygroup/subadmins
```

- Return the subadmins of the group: mygroup

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <status>ok</status>
    <statuscode>100</statuscode>
    <message/>
  </meta>
  <data>
    <element>Tom</element>
  </data>
</ocs>
```

Delete a group

Removes a group. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/groups/{groupid}`

- HTTP method: DELETE

Status codes:

- 100 - successful
- 101 - group does not exist
- 102 - failed to delete group

Example

```
$ curl -X DELETE http://admin:secret@example.com/ocs/v1.php/cloud/groups/mygroup
```

- Delete the group mygroup

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
  <data/>
</ocs>
```

7.10.3 Instruction set for apps

Getlist of apps

Returns a list of apps installed on the Nextcloud server. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: ocs/v1.php/cloud/apps/

- HTTP method: GET
- url argument: filter, string - optional (enabled or disabled)

Status codes:

- 100 - successful
- 101 - invalid input data

Example

```
$ curl -X GET http://admin:secret@example.com/ocs/v1.php/cloud/apps?filter=enabled
```

- Gets enabled apps

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statusCode>100</statusCode>
    <status>ok</status>
  </meta>
  <data>
    <apps>
      <element>files</element>
      <element>provisioning_api</element>
    </apps>
  </data>
</ocs>
```

Get app info

Provides information on a specific application. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: ocs/v1.php/cloud/apps/{appid}

- HTTP method: GET

Status codes:

- 100 - successful

Example

```
$ curl -X GET http://admin:secret@example.com/ocs/v1.php/cloud/apps/files
```

- Get app info for the files app

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statusCode>100</statusCode>
    <status>ok</status>
  </meta>
  <data>
    <info/>
    <remote>
      <files>appinfo/remote.php</files>
      <webdav>appinfo/remote.php</webdav>
      <filesync>appinfo/filesync.php</filesync>
    </remote>
    <public/>
    <id>files</id>
```

(continues on next page)

(continued from previous page)

```

<name>Files</name>
<description>File Management</description>
<licence>AGPL</licence>
<author>Robin Appelman</author>
<require>4.9</require>
<shipped>true</shipped>
<standalone></standalone>
<default_enable></default_enable>
<types>
  <element>filesystem</element>
</types>
</data>
</ocs>

```

Enable an app

Enable an app. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/apps/{appid}`

- HTTP method: POST

Status codes:

- 100 - successful

Example

```
$ curl -X POST http://admin:secret@example.com/ocs/v1.php/cloud/apps/files_texteditor
```

- Enable the files_texteditor app

XML output

```

<?xml version="1.0"?>
<ocs>
  <meta>
    <statuscode>100</statuscode>
    <status>ok</status>
  </meta>
</ocs>

```

Disable an app

Disables the specified app. Authentication is done by sending a Basic HTTP Authorization header.

Syntax: `ocs/v1.php/cloud/apps/{appid}`

- HTTP method: DELETE

Status codes:

- 100 - successful

Example

```
$ curl -X DELETE http://admin:secret@example.com/ocs/v1.php/cloud/apps/files_texteditor
```

- Disable the `files_texteditor` app

XML output

```
<?xml version="1.0"?>
<ocs>
  <meta>
    <statusCode>100</statusCode>
    <status>ok</status>
  </meta>
</ocs>
```

FILE SHARING AND MANAGEMENT

8.1 File Sharing

Nextcloud users can share files with their Nextcloud groups and other users on the same Nextcloud server, with Nextcloud users on *other Nextcloud servers*, and create public shares for people who are not Nextcloud users. You have control of a number of user permissions on file shares.

Configure your sharing policy on your Admin page in the Sharing section.

Sharing ⁱ

As admin you can fine-tune the sharing behavior. Please see the documentation for more information.

☒ Allow apps to use the Share API

☒ Set default expiration date for shares

Expire after days ☐ Enforce expiration date

☒ Allow users to share via link

☒ Allow public uploads

☐ Always ask for a password

☐ Enforce password protection

☒ Set default expiration date for link shares

Expire after days ☐ Enforce expiration date

☒ Allow resharing

☒ Allow sharing with groups

☐ Restrict users to only share with users in their groups

☒ Exclude groups from sharing

These groups will still be able to receive shares, but not to initiate them.

☒ Allow username autocompletion in share dialog. If this is disabled the full username or email address needs to be entered.

☒ Restrict username autocompletion to users within the same groups

☒ Show disclaimer text on the public link upload page. (Only shown when the file list is hidden.)

This text will be shown on the public link upload page when the file list is hidden.

Default share permissions

☒ Create ☒ Change ☒ Delete ☒ Reshare

- Check **Allow apps to use the Share API** to enable users to share files. If this is not checked, no users can create file shares.
- Check **Set default expiration date for shares** to set a default expiration date on local user and group shares.
- Check **Enforce expiration date** to always enforce the configured expiration date on local user and group shares.

Note: Users will not be able to set the expiration date further in the future than the enforced expiration date, although they will be able to set a more recent date. Also note that users will be able to update the expiration date again at a later point. The expiration date is based on the current date and not on the share creation date. The user will be able to extend the expiration date again whenever a previous expiration date is close to be reached.

- Check `Allow users to share via link` to enable creating public shares for people who are not Nextcloud users via hyperlink.
- Check `Allow public uploads` to allow anyone to upload files to public shares.
- Check `Always ask for a password` to proactively ask a user to set a password for a share link.
- Check `Enforce password protection` to force users to set a password on all public share links. This does not apply to local user and group shares.
- Check `Set default expiration date for link shares` to set a default expiration date on public shares.
- Check `Enforce expiration date` to always enforce the configured expiration date on public shares.

Note: Users will not be able to set the expiration date further in the future than the enforced expiration date, although they will be able to set a more recent date. Also note that users will be able to update the expiration date again at a later point. The expiration date is based on the current date and not on the share creation date. The user will be able to extend the expiration date again whenever a previous expiration date is close to be reached.

- Check `Allow resharing` to enable users to re-share files shared with them.
- Check `Allow sharing with groups` to enable users to share with groups.
- Check `Restrict users to only share with users in their groups` to confine sharing within group memberships.

Note: This setting does not apply to the Federated Cloud sharing feature. If *Federated Cloud Sharing* is enabled, users can still share items with any users on any instances (including the one they are on) via a remote share.

- Check `Exclude groups from sharing` to prevent members of specific groups from creating any file shares in those groups. When you check this, you'll get a dropdown list of all your groups to choose from. Members of excluded groups can still receive shares, but not create any.
- Check `Allow username autocompletion in share dialog` to enable auto-completion of Nextcloud usernames.
- Check `Restrict username autocompletion to users within the same groups` to limit username autocompletion to users from within the same groups as the share owner.
- Check `Show disclaimer text on the public link upload page` to set and show a disclaimer text on public links with hidden file lists.

With `Default share permissions` you are able to set the default permissions for user-shares (Create, Change, Delete and Reshare) without forcing them.

Note: Nextcloud does not preserve the mtime (modification time) of directories, though it does update the mtimes on

files. See [Wrong folder date when syncing](#) for discussion of this.

Note: There are more sharing options on config.php level available: Configuration Parameters

8.1.1 Distinguish between max expiration date and default expiration date

The expiration date which can be set and enforced in the settings above are the hard limit and the default value at the same time. Sometimes admins want to have a moderate default expire date, for example 7 days but make sure that the user can't extend it to more than 14 days.

In order to do so the user can set a enforced expiration date in the settings as described above and set the default value to something below the maximal possible expiration date with the following OCC commands:

```
occ config:app:set --value <DAYS> core internal_defaultExpDays
occ config:app:set --value <DAYS> core link_defaultExpDays
```

8.1.2 Get a notification before a share expires

Users can get a notification before a share expires. In order to do so a cronjob need to be configured which calls the following OCC command once a day:

```
occ sharing:expiration-notification
```

A notification will be send for all shares which expire within the next 24 hours.

8.1.3 Transferring files to another user

You may transfer files from one user to another with occ. This is useful when you have to remove a user. Be sure to transfer the files before you delete the user! This transfers all files from user1 to user2, and the shares and metadata info associated with those files (shares, tags, comments, etc). Trashbin contents are not transferred:

```
occ files:transfer-ownership user1 user2
```

(See [Using the occ command](#) for a complete occ reference.)

Users may also transfer files or folders selectively by themselves. See [user documentation](#) for details.

8.1.4 Creating persistent file Shares

When a user is deleted, their files are also deleted. As you can imagine, this is a problem if they created file shares that need to be preserved, because these disappear as well. In Nextcloud files are tied to their owners, so whatever happens to the file owner also happens to the files.

One solution is to create persistent shares for your users. You can retain ownership of them, or you could create a special user for the purpose of establishing permanent file shares. Simply create a shared folder in the usual way, and share it with the users or groups who need to use it. Set the appropriate permissions on it, and then no matter which users come and go, the file shares will remain. Because all files added to the share, or edited in it, automatically become owned by the owner of the share regardless of who adds or edits them.

8.2 Configuring Federation Sharing

Federated Cloud Sharing is now managed by the Federation app (9.0+), and is now called Federation sharing. When you enable the Federation app you can easily and securely link file shares between Nextcloud servers, in effect creating a cloud of Nextclouds.

8.2.1 Creating a new Federation Share

Follow these steps to create a new Federation share between two Nextcloud servers. This requires no action by the user on the remote server; all it takes is a few steps on the originating server.

1. Enable the Federation app.
2. Go to your Nextcloud Admin page and scroll to the Sharing section. Verify that **Allow users on this server to send shares to other servers** and **Allow users on this server to receive shares from other servers** are enabled.
3. Now go to the Federation section. By default, **Add server automatically once a federated share was created successfully** is checked. The Federation app supports creating a list of trusted Nextcloud servers, which allows the trusted servers to exchange user directories and auto-complete the names of external users when you create shares. If you do not want this enabled, then un-check it.


Trusted servers

Federation allows you to connect with other trusted servers to exchange the user directory. For example this will be used to auto-complete external users for federated sharing.


☒ Add server automatically once a federated share was created successfully

+ Add trusted server

4. Now go to your Files page and select a folder to share. Click the share icon, and then enter the username and URL of the user on the remote Nextcloud server. In this example, that is `freda@https://example.com/nextcloud`. When Nextcloud verifies the link, it displays it with the **(remote)** label. Click on this label to establish the link.



5. When the link is successfully completed, you have a single share option, and that is **can edit**.



You may disconnect the share at any time by clicking the trash can icon.

8.2.2 Configuring trusted Nextcloud servers

You may create a list of trusted Nextcloud servers for Federation sharing. This allows your linked Nextcloud servers to share user directories, and to auto-fill user names in share dialogs. If **Add server automatically once a federated share was created successfully** is enabled on your Admin page, servers will be automatically added to your trusted list when you create new Federation shares.

You may also enter Nextcloud server URLs in the **Add Nextcloud Server** field. The yellow light indicates a successful connection, with no user names exchanged. The green light indicates a successful connection with user names exchanged. A red light means the connection failed.

Federation

Nextcloud Federation allows you to connect with other trusted Nextclouds to exchange the user directory. For example this will be used to auto-complete external users for federated sharing.

☒ Add server automatically once a federated share was created successfully


Trusted Nextcloud Servers

Nextcloud Server


 http://localhost/federation/	
 https://server2	
 https://server3	

8.2.3 Creating Federation Shares via public Link Share


Check the **Share link** entry to expose more sharing options (which are described more fully in [File Sharing](#)). You may create a Federation share by allowing Nextcloud to create a public link for you, and then email it to the person you want to create the share with.




You may optionally set a password and expiration date on it. When your recipient receives your email they must click the link, or copy it to a Web browser. They will see a page displaying a thumbnail of the file, with a button to **Add to your Nextcloud**.



Your recipient should click the **Add to your Nextcloud** button. On the next screen your recipient needs to enter the URL to their Nextcloud server, and then press the return key.



Your recipient has to take one more step, and that is to confirm creating the federated cloud share link by clicking the **Accept** button.



Un-check the `Share link` checkbox to disable any federated cloud share created this way.

8.2.4 Configuration tips

The Sharing section on your Admin page allows you to control how your users manage federated cloud shares:

- Check `Enforce password protection` to require passwords on link shares.
- Check `Set default expiration date` to require an expiration date on link shares.
- Check `Allow public uploads` to allow two-way file sharing.

Your Apache Web server must have `mod_rewrite` enabled, and you must have `trusted_domains` correctly configured in `config.php` to allow external connections (see [Installation wizard](#)). Consider also enabling SSL to encrypt all traffic between your servers .

Your Nextcloud server creates the share link from the URL that you used to log into the server, so make sure that you log into your server using a URL that is accessible to your users. For example, if you log in via its LAN IP address, such as `http://192.168.10.50`, then your share URL will be something like `http://192.168.10.50/nextcloud/index.php/s/jWfCfTVztGlWTJe`, which is not accessible outside of your LAN. This also applies to using the server name; for access outside of your LAN you need to use a fully-qualified domain name such as `http://myserver.example.com`, rather than `http://myserver`.

8.3 Uploading big files > 512MB

The default maximum file size for uploads is 512MB. You can increase this limit up to what your filesystem and operating system allows. There are certain hard limits that cannot be exceeded:

- < 2GB on 32Bit OS-architecture
- < 2GB with IE6 - IE8
- < 4GB with IE9 - IE11

64-bit filesystems have much higher limits; consult the documentation for your filesystem.

Note: The Nextcloud sync client is not affected by these upload limits as it is uploading files in smaller chunks. See [Client documentation](#) for more information on configuration options.

8.3.1 System configuration

- Make sure that the latest version of PHP is installed
- Disable user quotas, which makes them unlimited
- Your temp file or partition has to be big enough to hold multiple parallel uploads from multiple users; e.g. if the max upload size is 10GB and the average number of users uploading at the same time is 100: temp space has to hold at least 10x100 GB

8.3.2 Configuring your Web server

Note: Nextcloud comes with its own `nextcloud/.htaccess` file. Because `php-fpm` can't read PHP settings in `.htaccess` these settings must be set in the `nextcloud/.user.ini` file.

Set the following two parameters inside the corresponding `php.ini` file (see the **Loaded Configuration File** section of *PHP version and information* to find your relevant `php.ini` files)

```
php_value upload_max_filesize 16G
php_value post_max_size 16G
```

The `upload_max_filesize` and `post_max_size` settings may not apply to file uploads through WebDAV single file PUT requests or [Chunked file uploads](#). For those, PHP and webserver timeouts are the limiting factor on the upload size.

Adjust these values for your needs. If you see PHP timeouts in your logfiles, increase the timeout values, which are in seconds:

```
php_value max_input_time 3600
php_value max_execution_time 3600
```

The `mod_reqtimeout` Apache module could also stop large uploads from completing. If you're using this module and getting failed uploads of large files either disable it in your Apache config or raise the configured `RequestReadTimeout` timeouts.

There are also several other configuration options in your Web server config which could prevent the upload of larger files. Please see the manual of your Web server for how to configure those values correctly:

Apache

- `LimitRequestBody`
- `SSLRenegBufferSize`

Apache with mod_fcgid

- `FcgidMaxRequestInMem`
- `FcgidMaxRequestLen`

Note: If you are using Apache/2.4 with mod_fcgid, as of February/March 2016, `FcgidMaxRequestInMem` still needs to be significantly increased from its default value to avoid the occurrence of segmentation faults when uploading big files. This is not a regular setting but serves as a workaround for [Apache with mod_fcgid bug #51747](#).

Setting `FcgidMaxRequestInMem` significantly higher than normal may no longer be necessary, once bug #51747 is fixed.

nginx

- `client_max_body_size`
- `fastcgi_read_timeout`
- `client_body_temp_path`

Since nginx 1.7.11 a new config option `fastcgi_request_buffering` is available. Setting this option to `fastcgi_request_buffering off`; in your nginx config might help with timeouts during the upload. Furthermore it helps if you're running out of disc space on the tmp partition of your system.

Note: Make sure that `client_body_temp_path` points to a partition with adequate space for your upload file size, and on the same partition as the `upload_tmp_dir` or `tempdirectory` (see below). For optimal performance, place these on a separate hard drive that is dedicated to swap and temp storage.

If your site is behind a nginx frontend (for example a loadbalancer):

By default, downloads will be limited to 1GB due to `proxy_buffering` and `proxy_max_temp_file_size` on the frontend.

- If you can access the frontend's configuration, disable `proxy_buffering` or increase `proxy_max_temp_file_size` from the default 1GB.
- If you do not have access to the frontend, set the `X-Accel-Buffering` header to `add_header X-Accel-Buffering no`; on your backend server.

8.3.3 Configuring PHP

If you don't want to use the Nextcloud `.htaccess` or `.user.ini` file, you may configure PHP instead. Make sure to comment out any lines `.htaccess` pertaining to upload size, if you entered any.

If you are running Nextcloud on a 32-bit system, any `open_basedir` directive in your `php.ini` file needs to be commented out.

Set the following two parameters inside `php.ini`, using your own desired file size values:

```
upload_max_filesize = 16G
post_max_size = 16G
```

Tell PHP which temp directory you want it to use:

```
upload_tmp_dir = /var/big_temp_file/
```

Output Buffering must be turned off in `.htaccess` or `.user.ini` or `php.ini`, or PHP will return memory-related errors:

- `output_buffering = 0`

8.3.4 Configuring Nextcloud

As an alternative to the `upload_tmp_dir` of PHP (e.g. if you don't have access to your `php.ini`) you can also configure a temporary location for uploaded files by using the `tempdirectory` setting in your `config.php` (See [Configuration Parameters](#)).

If you have configured the `session_lifetime` setting in your `config.php` (See [Configuration Parameters](#)) file then make sure it is not too low. This setting needs to be configured to at least the time (in seconds) that the longest upload will take. If unsure remove this completely from your configuration to reset it to the default shown in the `config.sample.php`.

8.3.5 Adjust chunk size on Nextcloud side

For upload performance improvements in environments with high upload bandwidth, the server's upload chunk size may be adjusted:

```
sudo -u www-data php occ config:app:set files max_chunk_size --value 20971520
```

Put in a value in bytes (in this example, 20MB). Set `--value 0` for no chunking at all.

Default is 10485760 (10 MB).

8.3.6 Large file upload on object storage


[Chunked file uploads](#) do have a larger space consumption on the temporary folder when processing those uploads on object storage as the individual chunks get downloaded from the storage and will be assembled to the actual file on the Nextcloud servers temporary directory. It is recommended to increase the size of your temp directory accordingly and also ensure that request timeouts are high enough for PHP, webserver or any load balancers involved.

8.4 Providing default files


You may distribute a set of default files and folders to all users by placing them in directory that is readable by the webserver user. This allows you to overwrite the files that are shipped by default with Nextcloud in `core/skeleton`. That custom directory should then be configured in the `config.php` via the configuration option `skeletondirectory` (see [Configuration Parameters](#)). Leave empty to not copy any skeleton files.

These files will be copied only to new users after their initial login, and existing users will not see files that are added to this directory after their first login. The files in the `skeleton` directory are copied into the users data directories, so they may change and delete the files without affecting the originals.

This screenshot shows a set of photos in the `skeleton` directory.



They appear on the user's Nextcloud Files page just like any other files.



Note: Overwriting the files in `core/skeleton` is not recommended, because those changes will be overwritten on the next update of the Nextcloud server.

8.5 Configuring Object Storage as Primary Storage

Nextcloud allows to configure object storages like OpenStack Swift or Amazon Simple Storage Service (S3) or any compatible S3-implementation (e.g. Minio or Ceph Object Gateway) as primary storage replacing the default storage of files.

By default, files are stored in `nextcloud/data` or another directory configured in the `config.php` of your Nextcloud instance. This data directory might still be used for compatibility reasons)

8.5.1 Implications

When using an object store as primary storage, Nextcloud assumes exclusive access over the bucket being used.

Contrary to using an object store as external storage, when an object store is used as primary storage, no metadata (names, directory structures, etc) is stored in the object store. The metadata is only stored in the database and the object store only holds the file content by unique identifier.

Because of this primary object stores usually perform better than when using the same object store as external storage but it restricts being able to access the files from outside of Nextcloud.

8.5.2 Configuration

Primary object stores need to be configured in `config.php` by specifying the objectstore backend and any backend specific configuration.

Note: Configuring a primary object store on an existing Nextcloud instance will make all existing files on the instance inaccessible.

The configuration has the following structure:

```
'objectstore' => [
    'class' => 'Object\\Storage\\Backend\\Class',
    'arguments' => [
        ...
    ],
],
```

OpenStack Swift

The OpenStack Swift backend mounts a container on an OpenStack Object Storage server into the virtual filesystem.

The class to be used is `\\OC\\Files\\ObjectStore\\Swift`

Both openstack v2 and v3 authentication are supported,

V2 Authentication:

```
'objectstore' => [
    'class' => '\\OC\\Files\\ObjectStore\\Swift',
    'arguments' => [
        'username' => 'username',
        'password' => 'Secr3tPaSSWoRdt7',
        // the container to store the data in
        'bucket' => 'nextcloud',
        'autocreate' => true,
        'region' => 'RegionOne',
        // The Identity / Keystone endpoint
        'url' => 'http://example.com/v2.0',
        // optional on some swift implementations
        'tenantName' => 'username',
        'serviceName' => 'swift',
        // The Interface / url Type, optional
        'urlType' => 'internal'
    ],
],
```

V3 Authentication:

```
'objectstore' => [
    'class' => 'OC\\Files\\ObjectStore\\Swift',
    'arguments' => [
        'autocreate' => true,
        'user' => [
            'name' => 'UserName',
            'password' => 'Secr3tPaSSWoRdt7',
            'domain' => [
                'name' => 'Default',
            ],
        ],
    ],
    'scope' => [
        'project' => [
            'name' => 'TenantName',
            'domain' => [
                'name' => 'Default',
            ],
        ],
    ],
    'serviceName' => 'swift',
    'region' => 'regionOne',
    'url' => 'http://example.com/v3',
    'bucket' => 'nextcloud',
],
```

(continues on next page)

(continued from previous page)

],

Simple Storage Service (S3)

The simple storage service (S3) backend mounts a bucket on an Amazon S3 object storage or compatible implementation (e.g. Minio or Ceph Object Gateway) into the virtual filesystem.

The class to be used is `\\OC\\Files\\ObjectStore\\S3`

```
'objectstore' => [
    'class' => '\\OC\\Files\\ObjectStore\\S3',
    'arguments' => [
        'bucket' => 'nextcloud',
        'autocreate' => true,
        'key' => 'EJ39ITYZEUH5BGWDRUFY',
        'secret' => 'M5MrXTRjkyMaxXPe2FRXMTfTfbKEEnZCu+7uRTVSj',
        'hostname' => 'example.com',
        'port' => 1234,
        'use_ssl' => true,
        'region' => 'optional',
        // required for some non Amazon S3 implementations
        'use_path_style'=>true
    ],
],
```

Note: Not all configuration options are required for all S3 servers. Overriding the hostname, port and region of your S3 server is only required for non-Amazon implementations, which in turn usually don't require the region to be set.

Note: `use_path_style` is usually not required (and is, in fact, incompatible with newer Amazon datacenters), but can be used with non-Amazon servers where the DNS infrastructure cannot be controlled. Ordinarily, requests will be made with `http://bucket.hostname.domain/`, but with path style enabled, requests are made with `http://hostname.domain/bucket` instead.

8.5.3 Multibucket Object Store

It's possible to configure Nextcloud to distribute the data over multiple buckets for scalability purposes.

To setup multiple buckets, use `'objectstore_multibucket'` storage backend in `config.php`:

```
'objectstore_multibucket' => [
    'class' => 'Object\\Storage\\Backend\\Class',
    'arguments' => [
        // optional, defaults to 64
        'num_buckets' => 64,
        // will be postfixed by an integer in the range from 0 to (num_nuckets-1)
        'bucket' => 'nextcloud_',
        ...
    ],
],
```

(continues on next page)

(continued from previous page)

```
],  
],
```

Multibucket object store backend maps every user to a range of buckets and saves all files for that user in their corresponding bucket.

Note: While it is possible to change the number of buckets used by an existing Nextcloud instance, the user-to-buckets mapping is only created once, so only newly created users will be mapped to the updated range of buckets.

You can find out more information about upscaling with object storage and Nextcloud in the [Nextcloud customer portal](#).


8.6 Configuring External Storage (GUI)

The External Storage Support application enables you to mount external storage services and devices as secondary Nextcloud storage devices. You may also allow users to mount their own external storage services.

For configuration of external storages via occ command, see [occ documentation](#).

8.6.1 Enabling External Storage Support

The External storage support application is enabled on your Apps page.



8.6.2 Storage configuration

To create a new external storage mount, select an available backend from the dropdown **Add storage**. Each backend has different required options, which are configured in the configuration fields.

External storages i

External storage enables you to mount external storage services and devices as secondary Nextcloud storage dev may also allow users to mount their own external storage services.

Folder name	External storage	Authentication	Configuration
Folder name	Add storage ▼		

Global credentials

Global credentials can be used to

Amazon S3

FTP

Nextcloud

OpenStack Object Storage

SFTP

SMB / CIFS

WebDAV

External storages that have the same credentials.

Each backend may also accept multiple authentication methods. These are selected with the dropdown under **Authentication**. Different backends support different authentication mechanisms; some specific to the backend, others are more generic. See [External Storage authentication mechanisms](#) for more detailed information.

When you select an authentication mechanism, the configuration fields change as appropriate for the mechanism. The SFTP backend, for one example, supports **username and password**, **Log-in credentials**, **save in session**, and **RSA public key**.

External Storage

Folder name	External storage	Authentication	Configuration
SFTP	SFTP	Username and password ▼ Username and password Log-in credentials, save in session RSA public key	Host Root Username Password

Required fields are marked with a red border. When all required fields are filled, the storage is automatically saved. A green dot next to the storage row indicates the storage is ready for use. A red or yellow icon indicates that Nextcloud could not connect to the external storage, so you need to re-check your configuration and network availability.

If there is an error on the storage, it will be marked as unavailable for ten minutes. To re-check it, click the colored icon or reload your Admin page.

8.6.3 Usage of variables for mount paths

The external storage mounting mechanism accepts variables in the mount path.

Use `$user` for automatic substitution with the logged in user's username.

Use `$home` for automatic substitution with a configurable home directory variable (requires LDAP, see *Special attributes* in the LDAP configuration documentation for details)

In the following example, the mount point for a logged in user “alice” would substitute to `/opt/userDirectories/alice/myPictures`.


Configuration

```
/opt/userDirectories/$user/myPictures
```

8.6.4 User and group permissions

A storage configured in a user's Personal settings is available only to the user that created it. A storage configured in the Admin settings is available to all users by default, and it can be restricted to specific users and groups in the **Available for** field.

Available for




8.6.5 Mount options

The Overflow menu (three dots) exposes the settings and trashcan. Click the trashcan to delete the mountpoint. The settings button allows you to configure each storage mount individually with the following options:

- Encryption
- Previews
- Enable Sharing
- Filesystem check frequency (Never, Once per direct access)
- Mac NFD Compatability
- Read Only

The **Encryption** checkbox is visible only when the Encryption app is enabled. Note that server-side encryption is not available for other Nextcloud servers used as external storage.

Enable Sharing allows the Nextcloud admin to enable or disable sharing on individual mountpoints. When sharing is disabled the shares are retained internally, so that you can re-enable sharing and the previous shares become available again. Sharing is disabled by default.



8.6.6 Using self-signed certificates

When using self-signed certificates for external storage mounts the certificate must be imported into the personal settings of the user. Please refer to [Nextcloud HTTPS External Mount](#) for more information.

8.6.7 Available storage backends

The following backends are provided by the external storages app.

Amazon S3

To connect your Amazon S3 buckets to Nextcloud, you will need:

- S3 access key
- S3 secret key
- Bucket name

In the **Folder name** field enter a local folder name for your S3 mountpoint. If this does not exist it will be created.

In the **Available for** field enter the users or groups who have permission to access your S3 mount.

The **Enable SSL** checkbox enables HTTPS connections; using HTTPS is always highly-recommended.

External Storage

Folder name	External storage	Configuration	Available for
		AKIAIOSHDC77WFI	
			
		oc-files-wc	
 AmazonS3	Amazon S3 and compliant	Hostname (optional) Port (optional) Region (optional) ☒ Enable SSL ☒ ☐ Enable Path Style	All Users x

Optionally, you can override the hostname, port and region of your S3 server, which is required for non-Amazon servers such as Ceph Object Gateway.

Enable path style is usually not required (and is, in fact, incompatible with newer Amazon datacenters), but can be used with non-Amazon servers where the DNS infrastructure cannot be controlled. Ordinarily, requests will be made with `http://bucket.hostname.domain/`, but with path style enabled, requests are made with `http://hostname.domain/bucket` instead.

Legacy authentication is only required for S3 servers that only implement version 2 authentication, by default version 4 authentication will be used.

See [Configuring External Storage \(GUI\)](#) for additional mount options and information.

See [External Storage authentication mechanisms](#) for more information on authentication schemes.

FTP/FTPS

To connect to an FTP server, you will need:

- A folder name for your local mountpoint; the folder will be created if it does not exist
- The URL of the FTP server
- Port number (default: 21)
- FTP server username and password
- Remote Subfolder, the FTP directory to mount in Nextcloud. Nextcloud defaults to the root directory. If you specify a subfolder you must leave off the leading slash. For example, `public_html/images`

Your new mountpoint is available to all users by default, and you may restrict access by entering specific users or groups in the **Available for** field.

Optionally, Nextcloud can use FTPS (FTP over SSL) by checking **Secure ftps://**. This requires additional configuration with your root certificate if the FTP server uses a self-signed certificate.

External Storage

Folder name	External storage	Configuration	Available for
 FTP	FTP	ftp.example.com:22 username ●●●●●●●● public.html ☒ Secure ftps://	 support(group)

Note: The external storage FTP/FTPS needs the `allow_url_fopen` PHP setting to be set to 1. When having connection problems make sure that it is not set to 0 in your `php.ini`. See [PHP version and information](#) to learn how to find the right `php.ini` file to edit.

See [Configuring External Storage \(GUI\)](#) for additional mount options and information.

FTP uses the password authentication scheme; see [External Storage authentication mechanisms](#) for more information on authentication schemes.

Local

Local storages provide access to any directory on the Nextcloud server. Since this is a significant security risk, Local storage can only be configured in the Nextcloud admin settings. Non-admin users cannot create Local storage mounts.

Use this to mount any directory on your Nextcloud server that is outside of your Nextcloud `data/` directory. This directory must be readable and writable by your HTTP server user. These ownership and permission examples are on Ubuntu Linux:

```
sudo chown -R www-data:www-data /path/to/localdir
sudo chmod -R 0750 /path/to/localdir
```

Important: If you use consecutive commands, make sure, you are user `www-data`:

```
sudo -u www-data bash
cd /path/to/localdir
mkdir data
```

In the **Folder name** field enter the folder name that you want to appear on your Nextcloud Files page.

In the **Configuration** field enter the full filepath of the directory you want to mount.

In the **Available for** field enter the users or groups who have permission to access the mount. By default all users have access.

External Storage

Folder name	External storage	Configuration	Available for
 Local	Local	/shared/projects	 All Users ×

See *Configuring External Storage (GUI)* for additional mount options and information.

See *External Storage authentication mechanisms* for more information on authentication schemes.

Nextcloud

A Nextcloud storage is a specialized *WebDAV* storage, with optimizations for Nextcloud-Nextcloud communication. See the *WebDAV* documentation to learn how to configure a Nextcloud external storage.

When filling in the **URL** field, use the path to the root of the Nextcloud installation, rather than the path to the WebDAV endpoint. So, for a server at `https://example.com/nextcloud`, use `https://example.com/nextcloud` and not `https://example.com/nextcloud/remote.php/dav`.

See *Configuring External Storage (GUI)* for additional mount options and information.

See *External Storage authentication mechanisms* for more information on authentication schemes.

OpenStack Object Storage

OpenStack Object Storage is used to connect to an OpenStack Swift server, or to Rackspace. Two authentication mechanisms are available: one is the generic OpenStack mechanism, and the other is used exclusively for Rackspace, a provider of object storage that uses the OpenStack Swift protocol.

The OpenStack authentication mechanism uses the OpenStack Keystone v2 protocol. Your Nextcloud configuration needs:

- **Bucket.** This is user-defined; think of it as a subdirectory of your total storage. The bucket will be created if it does not exist.
- **Username** of your account.
- **Password** of your account.
- **Tenant name** of your account. (A tenant is similar to a user group.)
- **Identity Endpoint URL**, the URL to log in to your OpenStack account.

Folder name	External storage	Authentication	Configuration	A
			Service name	
			Region	
			myfiles	
			Request timeout (seconds)	
OpenStackObjectStorage	OpenStack Object Storage	OpenStack ▼	molly	
				
			foobar	
			http://devstack:5001	

The Rackspace authentication mechanism requires:

- **Bucket**
- **Username**
- **API key**.

You must also enter the term **cloudFiles** in the **Service name** field.

Folder name	External storage	Authentication	Configuration	A
			cloudFiles	
			Region	
			myfiles	
			Request timeout (seconds)	
OpenStackObjectStorage	OpenStack Object Storage	Rackspace ▼	molly	
				

It may be necessary to specify a **Region**. Your region should be named in your account information, and you can read about Rackspace regions at [About Regions](#).

The timeout of HTTP requests is set in the **Request timeout** field, in seconds.

See *Configuring External Storage (GUI)* for additional mount options and information.

See *External Storage authentication mechanisms* for more information on authentication schemes.

SFTP

Nextcloud's SFTP (SSH File Transfer Protocol) backend supports both password and public key authentication.

The **Host** field is required; a port can be specified as part of the **Host** field in the following format: `hostname.domain:port`. The default port is 22 (SSH).

For public key authentication, you can generate a public/private key pair from your **SFTP with secret key login** configuration.

External Storage

Folder name	External storage	Authentication	Configuration
SFTP	SFTP	Username and password Username and password Log-In credentials, save in session RSA public key	Host Root Username Password

After generating your keys, you need to copy your new public key to the destination server to `.ssh/authorized_keys`. Nextcloud will then use its private key to authenticate to the SFTP server.

The default **Remote Subfolder** is the root directory (`/`) of the remote SFTP server, and you may enter any directory you wish.

See *Configuring External Storage (GUI)* for additional mount options and information.

See *External Storage authentication mechanisms* for more information on authentication schemes.

SMB/CIFS

Nextcloud can connect to Windows file servers or other SMB-compatible servers with the SMB/CIFS backend.

Note: The SMB/CIFS backend requires `smbclient` or the PHP `smbclient` module to be installed on the Nextcloud server. The PHP `smbclient` module is preferred, but either will work. These should be included in any Linux distribution. (See [PECL smbclient](#) if your distro does not include them.)

You need the following information:

- Folder name for your local mountpoint.
- Host: The URL of the Samba server.
- Username: The username or `domain\username` (see below) used to login to the Samba server.
- Password: the password to login to the Samba server.
- Share: The share on the Samba server to mount.

- Remote Subfolder: The remote subfolder inside the Samba share to mount (optional, defaults to /). To assign the Nextcloud logon username automatically to the subfolder, use \$user instead of a particular subfolder name.
- And finally, the Nextcloud users and groups who get access to the share.

Optionally, you can specify a **Domain**. This is useful in cases where the SMB server requires a domain and a username, and an advanced authentication mechanism like session credentials is used so that the username cannot be modified. This is concatenated with the username, so the backend gets domain\username

Note: For improved reliability and performance, we recommended installing `libsmbclient-php`, a native PHP module for connecting to SMB servers.

The screenshot shows the 'SMB / CIFS' configuration interface. On the left, there's a green status indicator and a 'smbcifs' label. In the center, a dropdown menu for 'Session credentials' is open, showing two options: 'Username and password' and 'Session credentials'. To the right, there are input fields for 'smbserver', 'users', '/shared', and 'Domain'. A search box on the far right contains the text 'All users. Type to select'.

See *Configuring External Storage (GUI)* for additional mount options and information.

See *External Storage authentication mechanisms* for more information on authentication schemes.

SMB update notifications

Nextcloud can use smb update notifications to listen for changes made to a configured SMB/CIFS storage and detect external changes made to the storage in near real-time.

Note: Due to limitations of linux based SMB servers, this feature only works reliably on Windows SMB servers.

Note: Using update notifications requires `smbclient` 4.x or newer. Due to limitations with the `smbclient` PHP module, the `smbclient` binary is required even when using the PHP module.

To start listening to update notifications, start the `occ` command like this:

```
occ files_external:notify <mount_id>
```

You can find the mount id for a specific storage using `occ files_external:list`

On default this command shows no output, can you see the list of detected changes by passing the `-v` option to the command.

SMB authentication

Update notifications are not supported when using ‘Login credentials, save in session’ authentication. Using login credentials is only supported with ‘Login credentials, save in database’.

Even when using ‘Login credentials, save in database’ or ‘User entered, stored in database’ authentication the notify process can not use the credentials saved to attach to the smb shares because the notify process does not run in the context of a specific user in those cases you can provide the username and password using the `--username` and `--password` arguments.

Decrease sync delay

Any updates detected by the notify command will only be synced to the client after the Nextcloud cron job has been executed (usually every 15 minutes). If this interval is too high for your use case, you can decrease it by running `occ files:scan --unscanned --all` at the desired interval. Note that this might increase the server load and you’ll need to ensure that there is no overlap between runs.

Hidden files upload failure or not shown

If you have the configuration `hide dot files = Yes`, you will not be able to upload a hidden file (dot file) nor will you be able to show hidden files on your filelist (even if the ‘show hidden file’ option is checked on the nextcloud settings. Make sure you have the following option in your configuration: `hide dot files = No`

WebDAV

Use this backend to mount a directory from any WebDAV server, or another Nextcloud server.

You need the following information:

- Folder name: The name of your local mountpoint.
- The URL of the WebDAV or Nextcloud server.
- Username and password for the remote server
- Secure <https://>: We always recommend <https://> for security, though you can leave this unchecked for <http://>.

Optionally, a Remote Subfolder can be specified to change the destination directory. The default is to use the whole root.

The screenshot shows the WebDAV configuration form in Nextcloud. On the left, there is a green status indicator and the label 'oc-remote'. The main form area is titled 'ownCloud'. It contains the following fields:

- URL: `https://remoteserve`
- Username: `admin`
- Password: `.....`
- Subfolder: `/`
- Secure <https://>: ☐ (unchecked)

On the right side of the form, there is a button labeled 'All Users x'.

Note: CPanel users should install [Web Disk](#) to enable WebDAV functionality.

See *Configuring External Storage (GUI)* for additional mount options and information.

See *External Storage authentication mechanisms* for more information on authentication schemes.

Note: A non-blocking or correctly configured SELinux setup is needed for these backends to work. Please refer to the *SELinux configuration*.

8.6.8 Allow users to mount external Storage

Check **Enable User External Storage** to allow your users to mount their own external storage services, and check the backends you want to allow. Beware, as this allows a user to make potentially arbitrary connections to other services on your network!

- ☒ Allow users to mount external storage
 - ☐ FTP
 - ☐ WebDAV
 - ☒ Nextcloud
 - ☐ SFTP
 - ☒ Amazon S3
 - ☐ OpenStack Object Storage
 - ☐ SMB / CIFS

8.6.9 Adding files to external storages

We recommend configuring the background job **Webcron** or **Cron** (see *Background jobs*) to enable Nextcloud to automatically detect files added to your external storages.

Nextcloud may not always be able to find out what has been changed remotely (files changed without going through Nextcloud), especially when it's very deep in the folder hierarchy of the external storage.

You might need to setup a cron job that runs `sudo -u www-data php occ files:scan --all` (or replace “--all” with the user name, see also *Using the occ command*) to trigger a rescan of the user's files periodically (for example every 15 minutes), which includes the mounted external storage.

8.7 External Storage authentication mechanisms

Nextcloud storage backends accept one or more authentication schemes such as passwords, OAuth, or token-based, to name a few examples. Each authentication scheme may be implemented by combining multiple authentication mechanisms. Different mechanisms require different configuration parameters, depending on their behavior.

External storage

Folder name	External storage	Authentication	Configuration	Available for
SFTP	SFTP	Username and password ☒ Log-in credentials, save in session ☐ Log-in credentials, save in database ☐ User entered, store in database ☐ Global credentials ☐ RSA public key	Host Root	All users. Type to select user or group.
Folder name	Add storage			

☐ Allow users to mount external storage

Global credentials

Username Password Save

8.7.1 Special mechanisms

The **None** authentication mechanism requires no configuration parameters, and is used when a backend requires no authentication.

The **Built-in** authentication mechanism itself requires no configuration parameters, but is used as a placeholder for legacy storages that have not been migrated to the new system and do not take advantage of generic authentication mechanisms. The authentication parameters are provided directly by the backend.

8.7.2 Password-based mechanisms

The **Username and password** mechanism requires a manually-defined username and password. These get passed directly to the backend and are specified during the setup of the mount point.

The **Log-in credentials, save in session** mechanism uses the Nextcloud login credentials of the user to connect to the storage. These are not stored anywhere on the server, but rather in the user session, giving increased security. This method has some important drawbacks, since Nextcloud has no access to the storage credentials and therefore cannot perform any background tasks on the storage:

- Sharing is disabled
- Background file scanning does not work
- Background versions expiration does not work
- Desktop and mobile clients that use tokens to authenticate can not access those shares
- Other services that might request the file through a different request like Collabora Online or OnlyOffice will not be able to open files from that storage
- The method cannot be used with SAML/SSO authentication, because Nextcloud does not get a hold of any credentials whatsoever

The **Log-in credentials, save in database** mechanism uses the Nextcloud login credentials of the user to connect to the storage. These are stored in the database encrypted with the shared secret. This allows to share files from within this mount point.

- The method cannot be used with SAML/SSO authentication, because Nextcloud does not get a hold of any credentials whatsoever

The **User entered, store in database** mechanism work in the same way as the “Username and password” mechanism but the credentials need to be specified by each user individually. Before the first access to that mount point the user will be prompted to enter the credentials.

The **Global credentials** mechanism uses the general input field for “Global credentials” in the external storage settings section as source for the credentials instead of individual credentials for a mount point.

8.7.3 Public-key mechanisms

Currently only the RSA mechanism is implemented, where a public/private keypair is generated by Nextcloud and the public half shown in the GUI. The keys are generated in the SSH format, and are currently 1024 bits in length. Keys can be regenerated with a button in the GUI.

The screenshot shows the 'Authentication' and 'Configuration' tabs. Under 'Authentication', 'RSA public key' is selected. Under 'Configuration', there are four input fields: 'Host', 'Root', 'Username', and a field containing 'ssh-rsa AAAAB3NzaC1'. Below these fields is a 'Generate keys' button.

8.8 Encryption configuration

The primary purpose of the Nextcloud server-side encryption is to protect users’ files on remote storage, such as Dropbox and Google Drive, and to do it easily and seamlessly from within Nextcloud.

Server-side encryption separates encryption of local and remote storage. This allows you to encrypt remote storage, such as Dropbox and Google, without having to also encrypt your home storage on your Nextcloud server.

Note: Nextcloud supports Authenticated Encryption for all newly encrypted files. See <https://hackerone.com/reports/108082> for more technical information about the impact.

For maximum security make sure to configure external storage with “Check for changes: Never”. This will let Nextcloud ignore new files not added via Nextcloud, so a malicious external storage administrator could not add new files to the storage without your knowledge. Of course, this is not wise if your external storage is subject to legitimate external changes.

Nextcloud server-side encryption encrypts files stored on the Nextcloud server, and files on remote storage that is connected to your Nextcloud server. Encryption and decryption are performed on the Nextcloud server. All files sent to remote storage will be encrypted by the Nextcloud server, and upon retrieval, decrypted before serving them to you and anyone you have shared them with.

Note: Encrypting files increases their size by roughly 35%, so you must take this into account when you are provisioning storage and setting storage quotas. User’s quotas are based on the unencrypted file size, and not the encrypted file size.

When files on external storage are encrypted in Nextcloud, you cannot share them directly from the external storage services, but only through Nextcloud sharing because the key to decrypt the data never leaves the Nextcloud server.

Nextcloud's server-side encryption generates a strong encryption key, which is unlocked by user's passwords. Your users don't need to track an extra password, but simply log in as they normally do. It encrypts only the contents of files, and not filenames and directory structures.

You should regularly backup all encryption keys to prevent permanent data loss. The encryption keys are stored in the following directories:

data/<user>/files_encryption Users' private keys and all other keys necessary to decrypt the users' files

data/files_encryption private keys and all other keys necessary to decrypt the files stored on a system wide external storage

When encryption is enabled, all files are encrypted and decrypted by the Nextcloud application, and stored encrypted on your remote storage. This protects your data on externally hosted storage. The Nextcloud admin and the storage admin will see only encrypted files when browsing backend storage.

Warning: Encryption keys are stored only on the Nextcloud server, eliminating exposure of your data to third-party storage providers. The encryption app does **not** protect your data if your Nextcloud server is compromised, and it does not prevent Nextcloud administrators from reading user's files. This would require client-side encryption, which this app does not provide. If your Nextcloud server is not connected to any external storage services then it is better to use other encryption tools, such as file-level or whole-disk encryption.

Note also that SSL terminates at or before Apache on the Nextcloud server, and all files will exist in an unencrypted state between the SSL connection termination and the Nextcloud code that encrypts and decrypts files. This is also potentially exploitable by anyone with administrator access to your server. Read [How Nextcloud uses encryption to protect your data](#) for more information.

8.8.1 Before enabling encryption

Plan very carefully before enabling encryption because it is not reversible via the Nextcloud Web interface. If you lose your encryption keys your files are not recoverable. Always have backups of your encryption keys stored in a safe location, and consider enabling all recovery options.

You have more options via the occ command (see *[occ encryption commands](#)*)

8.8.2 Enabling encryption

Nextcloud encryption consists of two parts. The base encryption system is enabled and disabled on your Admin page. First you must enable this, and then select an encryption module to load. Currently the only available encryption module is the Nextcloud Default Encryption Module.

First go to the **Server-side encryption** section of your Admin page and check **Enable server-side encryption**. You have one last chance to change your mind.

Server-side encryption ⁱ

Server-side encryption makes it possible to encrypt files which are uploaded to this server. This comes with limitations like a performance penalty, so enable this only if needed.

☒ Enable server-side encryption

Please read carefully before activating server-side encryption:

- Once encryption is enabled, all files uploaded to the server from that point forward will be encrypted at rest on the server. It will only be possible to disable encryption at a later date if the active encryption module supports that function, and all pre-conditions (e.g. setting a recover key) are met.
- Encryption alone does not guarantee security of the system. Please see documentation for more information about how the encryption app works, and the supported use cases.
- Be aware that encryption always increases the file size.
- It is always good to create regular backups of your data, in case of encryption make sure to backup the encryption keys along with your data.

This is the final warning: Do you really want to enable encryption?

Enable encryption

After clicking the **Enable Encryption** button you see the message “No encryption module loaded, please load a encryption module in the app menu”, so go to your Apps page to enable the Nextcloud Default Encryption Module.

Default encryption module

✓ Featured

by Bjoern Schiessle, Clark Tomlinson
AGPL-licensed

Enable

Return to your Admin page to see the Nextcloud Default Encryption Module added to the module selector, and automatically selected. Now you must log out and then log back in to initialize your encryption keys.

Server-side encryption

Server-side encryption makes it possible to encrypt files which are uploaded to this server. This comes with limitations like a performance penalty, so enable this only if needed.

☒ Enable server-side encryption

Select default encryption module:

☒ Default encryption module

When you log back in, there is a checkbox for enabling encryption on your home storage. This is checked by default. Un-check to avoid encrypting your home storage.

Server-side encryption

Server-side encryption makes it possible to encrypt files which are uploaded to this server. This comes with limitations like a performance penalty, so enable this only if needed.

☒ Enable server-side encryption

Select default encryption module:

☒ Default encryption module

Default encryption module

☒ Encrypt the home storage

Enabling this option encrypts all files stored on the main storage, otherwise only files on external storage will be encrypted

8.8.3 Sharing encrypted files

After encryption is enabled your users must also log out and log back in to generate their personal encryption keys. They will see a yellow warning banner that says “Encryption App is enabled but your keys are not initialized, please log-out and log-in again.”

Share owners may need to re-share files after encryption is enabled; users trying to access the share will see a message advising them to ask the share owner to re-share the file with them. For individual shares, un-share and re-share the file. For group shares, share with any individuals who can’t access the share. This updates the encryption, and then the share owner can remove the individual shares.

Can not decrypt this file, probably this is a shared file. Please ask the file owner to reshare the file with you.

8.8.4 Encrypting external mountpoints

You and your users can encrypt individual external mountpoints. You must have external storage enabled on your Admin page, and enabled for your users.

Encryption settings can be configured in the mount options for an external storage mount, see [Mount options \(Configuring External Storage \(GUI\)\)](#)

8.8.5 Enabling users file recovery keys

If you lose your Nextcloud password, then you lose access to your encrypted files. If one of your users loses their Nextcloud password their files are unrecoverable. You cannot reset their password in the normal way; you'll see a yellow banner warning "Please provide an admin recovery password, otherwise all user data will be lost".

To avoid all this, create a Recovery Key. Go to the Encryption section of your Admin page and set a recovery key password.

Server-side encryption *i*

☒ Enable server-side encryption

Select default encryption module:

☒ Default encryption module

Enable recovery key

The recovery key is an extra encryption key that is used to encrypt files. It allows recovery of a user's files if the user forgets his or her password.

●●●●●●●●

●●●●●●●●

Disable recovery key

Then your users have the option of enabling password recovery on their Personal pages. If they do not do this, then the Recovery Key won't work for them.

Encryption

Enable password recovery:


Enabling this option will allow you to reobtain access to your encrypted files in case of password loss

☒ Enabled

☐ Disabled

File recovery settings updated


For users who have enabled password recovery, give them a new password and recover access to their encrypted files by supplying the Recovery Key on the Users page.



The screenshot shows the top navigation bar with a search icon and the user 'admin'. Below it is a text input field labeled 'Admin Recovery Password'. Underneath are two dropdown menus: 'Group Admin for' with the value 'no group' and 'Quota' with the value 'Unlimited'.

You may change your Recovery Key password.

Change recovery key password:



The form consists of three password input fields, each with eight dots representing characters. The first field is labeled 'Old Recovery key password'. The second field is labeled 'New Recovery key password'. The third field is labeled 'Repeat New Recovery key password'. Below these fields is a button labeled 'Change Password'.

8.8.6 occ encryption commands

If you have shell access you may use the `occ` command to perform encryption operations, and you have additional options such as decryption and creating a single master encryption key. See [Encryption](#) for detailed instructions on using `occ`.

Get the current status of encryption and the loaded encryption module:

```
occ encryption:status
- enabled: false
- defaultModule: OC_DEFAULT_MODULE
```

This is equivalent to checking **Enable server-side encryption** on your Admin page:

```
occ encryption:enable
Encryption enabled

Default module: OC_DEFAULT_MODULE
```

List the available encryption modules:

```
occ encryption:list-modules
- OC_DEFAULT_MODULE: Default encryption module [default*]
```

Select a different default Encryption module (currently the only available module is `OC_DEFAULT_MODULE`):

```
occ encryption:set-default-module [Module ID].
```

The [module ID] is taken from the `encryption:list-modules` command.

Encrypt all data files for all users. For performance reasons, when you enable encryption on a Nextcloud server only new and changed files are encrypted. This command gives you the option to encrypt all files.

Run `occ`:

```
occ encryption:encrypt-all

You are about to start to encrypt all files stored in your Nextcloud.
It will depend on the encryption module you use which files get encrypted.
Depending on the number and size of your files this can take some time.
Please make sure that no users access their files during this process!

Do you really want to continue? (y/n)
```

When you type `y` it creates a key pair for each of your users, and then encrypts their files, displaying progress until all user files are encrypted.

Decrypt all user data files, or optionally a single user:

```
occ encryption:decrypt-all [username]
```

View current location of keys:

```
occ encryption:show-key-storage-root
Current key storage root: default storage location (data/)
```

Move keys to a different folder, either locally or on a different server. The folder must already exist, be owned by root and your HTTP group, and be restricted to root and your HTTP group. Further the folder needs to be located somewhere in your Nextcloud data folder, either physically, or as a mount. This example is for Ubuntu Linux. Note that the new folder is relative to your occ directory:

```
cd /your/nextcloud/data
mkdir keys
chown -R root:www-data keys
chmod -R 0770 keys
occ encryption:change-key-storage-root keys
Start to move keys:
  4 [=====]
Key storage root successfully changed to keys
```

Create a new master key. Use this when you have a single-sign on infrastructure. Use this only on fresh installations with no existing data, or on systems where encryption has not already been enabled. It is not possible to disable it:

```
occ encryption:enable-master-key
```

8.8.7 Disabling encryption

You may disable encryption only with occ. Make sure you have backups of all encryption keys, including users'. Put your Nextcloud server into maintenance mode, and then disable your encryption module with this command:

```
occ maintenance:mode --on
occ encryption:disable
occ encryption:decrypt-all
```

Take it out of maintenance mode when you are finished:

```
occ maintenance:mode --off
```

Warning: Disabling encryption without decrypting all the files will lead to decryption errors in the future as this state causes unpredictable behaviors.

Note: The `occ encryption:decrypt-all` can take a lot of time. You can run one user at a time like so: `occ encryption:decrypt-all <user-id>`.

8.8.8 Files not encrypted

Only the data in the files in `data/user/files` are encrypted, and not the filenames or folder structures. These files are never encrypted:

- Existing files in the trash bin & Versions. Only new and changed files after encryption is enabled are encrypted.
- Existing files in Versions
- Image thumbnails from the Gallery app
- Previews from the Files app

- The search index from the full text search app
- Third-party app data

There may be other files that are not encrypted; only files that are exposed to third-party storage providers are guaranteed to be encrypted.

8.8.9 LDAP and other external user back-ends

If you use an external user back-end, such as an LDAP or Samba server, and you change a user's password on the back-end, the user will be prompted to change their Nextcloud login to match on their next Nextcloud login. The user will need both their old and new passwords to do this. If you have enabled the Recovery Key then you can change a user's password in the Nextcloud Users panel to match their back-end password, and then, of course, notify the user and give them their new password.

8.8.10 Troubleshooting

Invalid private key for encryption app

This [issue](#) is being worked on. In the meantime there is a [workaround](#) which unfortunately is only suitable for administrators comfortable with the command line.

8.9 Encryption details

This document - provided by [SysEleven](#) - describes the server-side encryption scheme implemented by Nextcloud's default encryption module. This includes:

- the encryption and signature of files with a master key.
- the encryption and signature of files with a public sharing key.
- the encryption and signature of files with a recovery key.
- the encryption and signature of files with a user key.

These conventions apply throughout this document:

- Given file paths in this document are relative to the Nextcloud data directory that can be retrieved as `datadirectory` from the `config.php`.
- Placeholders are denoted as `$variable`. The variable has to be replaced with the appropriate information.
- Static strings are denoted as `"some string"`.
- The concatenation of strings is denoted as `$variable."some string"`.

Note: However, files that have been encrypted in Nextcloud versions 15 and lower may have slightly different structures.

8.9.1 Key type: master key

This is the default encryption mode in Nextcloud. With master key encryption enabled there is one central key that is used to secure the files handled by Nextcloud. The master key is protected by a password that can be generated by the server administrator. The advantage of the master key encryption is that the encryption is transparent to the users but has the disadvantage that the server administrator is able to decrypt user files without knowing any user password.

8.9.2 Key type: public sharing key

The public sharing key is used to secure files that have been publicly shared. The public sharing key is protected by a password that can be generated by the server administrator. The advantage of the public sharing key is that it is independent of the selected encryption mode so that Nextcloud is able to provide publicly shared files to outside parties.

8.9.3 Key type: recovery key

The recovery key is used to provide a restore mechanism in cases where the user key encryption is enabled, where the administrator has enabled the recovery key feature and the user has opted into using the recovery key feature. The recovery key can then be used to restore files when users have lost their passwords. The recovery key is protected by a recovery password that the server administrator should store securely. The advantage of the recovery key is that files can be recovered but has the disadvantage that the server administrator is able to decrypt user files without knowing any user password.

8.9.4 Key type: user key

User key encryption needs to be explicitly activated by calling `./occ encryption:disable-master-key`. In older versions of Nextcloud this had been enabled by default. With user key encryption enabled all users have their own user keys that are used to secure the files handled by Nextcloud. The user keys are protected by the user passwords. The advantage is that the server administrator is not able to decrypt user files without knowing any user password - unless the file is publicly shared or a recovery key is defined - but has the disadvantage that files are permanently lost if the users forget their user passwords - unless the files are (publicly) shared or a recovery key is defined.

Note: This method cannot be used with SAML authentication, because Nextcloud does not get a hold of any credentials whatsoever and therefore cannot use any users' passwords for encryption.

8.9.5 File type: public key file

Public key files contain RSA public keys that are used to encrypt/seal the share key files.

File format

Public key files are stored in PEM format.

File locations

The locations of public key files depend on their key type:

- master public key: "files_encryption/OC_DEFAULT_MODULE/master_". \$random. ".publicKey"
- public sharing public key: "files_encryption/OC_DEFAULT_MODULE/pubShare_". \$random. ".publicKey"
- recovery public key: "files_encryption/OC_DEFAULT_MODULE/recoveryKey_". \$random. ".publicKey"
- user public key: \$username. "/files_encryption/OC_DEFAULT_MODULE/" . \$username. ".publicKey"

8.9.6 File type: private key file

Private key files contain RSA private keys that are used to decrypt/unseal the share key files. The RSA private key is encrypted and signed with a password and stored in a format that is specific to the Nextcloud encryption module.

File format

The RSA private key that is represented in PEM format is encrypted and Base64 encoded (denoted as \$encryption). For the encryption an initialization vector of 16 bytes is selected (denoted as \$iv). Furthermore a hexadecimally encoded message authentication code of 64 bytes is calculated (denoted as \$signature). The resulting file contains:

```
"HBEGIN:cipher:AES-256-CTR:keyFormat:hash:HEND".
$encrypted."00iv00". $iv."00sig00". $signature."xxx"
```

File locations

The locations of private key files depend on their key type:

- master private key: "files_encryption/OC_DEFAULT_MODULE/master_". \$random. ".privateKey"
- public sharing private key: "files_encryption/OC_DEFAULT_MODULE/pubShare_". \$random. ".privateKey"
- recovery private key: "files_encryption/OC_DEFAULT_MODULE/recoveryKey_". \$random. ".privateKey"
- user private key: \$username. "/files_encryption/OC_DEFAULT_MODULE/" . \$username. ".privateKey"

8.9.7 File type: share key file

Share key files contain so-called envelope keys that are needed to decrypt the file key files. The envelope keys are created by `openssl_seal()` during the encryption and are needed for `openssl_open()` during the decryption. The envelope keys are encrypted with the public keys of the recipients that are allowed to read the actual files.

File format

The envelope keys are stored in binary format.

File locations

The locations of share key files depend on the type of the encrypted file:

- regular file: `$username."/files_encryption/keys/files/".$filename."/OC_DEFAULT_MODULE/".$recipient.".shareKey"`
- version file: *version files use the same location for the share key file as their regular file*
- trashed file: `$username."/files_encryption/keys/files_trashbin/files/".$filename.".d".$timestamp."/OC_DEFAULT_MODULE/".$recipient.".shareKey"`
- trashed version file: *trashed version files use the same location for the share key file as their trashed file*

8.9.8 File type: file key file

File key files contain symmetric keys used to encrypt the actual files. The file keys consist of 32 random bytes and are encrypted/sealed with the envelope keys stored in the share key files.

File format

The file keys are stored in binary format.

File locations

The locations of the file key files depend on the type of the encrypted file:

- regular file: `$username."/files_encryption/keys/files/".$filename."/OC_DEFAULT_MODULE/fileKey"`
- version file: *version files use the same location for the file key file as their regular file*
- trashed file: `$username."/files_encryption/keys/files_trashbin/files/".$filename.".d".$delete_timestamp."/OC_DEFAULT_MODULE/fileKey"`
- trashed version file: *trashed version files use the same location for the file key file as their trashed file*

8.9.9 File type: file

Files contain the actual file content. The file content is encrypted and signed with a password and stored in a format that is specific to the Nextcloud encryption module.

File format

The file content is split into blocks of 6072 bytes. Each block is encrypted and Base64 encoded (denoted as `$encryption[0..$n]`). For the encryption an initialization vector of 16 bytes is selected for each block (denoted as `$iv[0..$n]`). Furthermore a hexadecimally encoded message authentication code of 64 bytes is calculated for each block (denoted as `$signature[0..$n]`). An encrypted block has a total size of 8192 bytes (8096 bytes for `$encrypted[]`, 6 bytes for `"00iv00"`, 16 bytes for `$iv[]`, 7 bytes for `"00sig00"`, 64 bytes for `$signature[]` and 3 bytes for `"xxx"`). Only the last encrypted block may be shorter. The header of the encrypted file is padded with 8147 bytes of `"-"` (denoted as `$padding`) to a total of 8192 bytes. The resulting file contains:

```
"HBEGIN:cipher:AES-256-CTR:keyFormat:hash:HEND".$padding.
$encrypted[0]. "00iv00". $iv[0]. "00sig00". $signature[0]. "xxx".
$encrypted[1]. "00iv00". $iv[1]. "00sig00". $signature[1]. "xxx".
$encrypted[2]. "00iv00". $iv[2]. "00sig00". $signature[2]. "xxx".
[...]
$encrypted[$n]. "00iv00". $iv[$n]. "00sig00". $signature[$n]. "xxx"
```

File locations

The locations of the files depend on the type of the encrypted file:

- regular file: `$username."/files/" . $filename`
- version file: `$username."/files_versions/" . $filename . ".v" . $version_timestamp`
- trashed file: `$username."/files_trashbin/files/" . $filename . ".d" . $delete_timestamp`
- trashed version file: `$username."/files_trashbin/versions/" . $filename . ".v" . $version_timestamp . ".d" . $delete_timestamp`

8.9.10 Key generation: generate the key pair

The key pair has to be generated with the `openssl_pkey_new()` function. Then the private key and public key are extracted from the the key resource with the `openssl_pkey_export()` function.

8.9.11 Key generation: store the public key

The public key is written to the `$username.".publicKey"` file as documented in *File type: public key file*.

8.9.12 Key generation: store the private key

Derive the encryption key

The salt for the encryption key is derived by creating a raw SHA256 hash of `$uid.$instanceId.$instanceSecret` with the `hash()` function. `$instanceId` can be retrieved as `instanceid` from the `config.php`. `$instanceSecret` can be retrieved as `secret` from the `config.php`.

The encryption key is then derived by creating a raw SHA256-PBKDF2 hash of the password with the salt, 100.000 rounds and (by default) with a target size of 32 bytes (as required for AES-256-CTR) with the `hash_hmac()` function (denoted as `$passphrase`).

The used password depends on the key type:

- master private key: use `secret` from the `config.php`

- public sharing private key: use an empty password
- recovery private key: use the recovery password
- user private key: use the user password

Encrypt the private key

The initialization vector is generated as a random string of 16 bytes with the `random_bytes()` function (denoted as `$iv`). The private key is (by default) AES-256-CTR encrypted with the `$iv` and the `$passphrase` with the `openssl_encrypt()` function and returned as Base64 encoded without zero-padding (denoted as `$encrypted`).

Sign the private key

The message authentication key is derived by creating a raw SHA512 hash of `$passphrase.$version.$position.a` with the `hash()` function.

- `$version` is always "0".
- `$position` is always "0".

The signature is then derived by creating a hexadecimally encoded SHA256-HMAC of `$encrypted` and the message authentication key with the `hash_hmac()` function (denoted as `$signature`).

Store the private key

The private key is written to the `$username.".privateKey"` file with the derived `$encrypted`, `$iv` and `$signature` as documented in *File type: private key file*.

8.9.13 Encryption: generate the file key

Generate the file key

The file key is generated as a random string of 32 bytes with the `random_bytes()` function (denoted as `$filekey`).

Read the public key

The public keys of the recipients are read from the `$username.".publicKey"` files as documented in *File type: public key file*.

Encrypt/seal the file key

The file key is encrypted/sealed with the `openssl_seal()` function with the public keys. This returns the encrypted file key and the encrypted envelope keys for the recipients.

Store the file key

The encrypted file key is stored in the "fileKey" file as documented in *File type: file key file*.

Store the envelope keys

The encrypted envelope keys for the recipients are stored in the \$username." .shareKey" files as documented in *File type: share key file*.

8.9.14 Encryption: encrypt the file

Split the file

The file is split into 6072 bytes sized blocks. Only the last encrypted block may be shorter. Each block is referenced by its zero-based index within the file (denoted as \$position).

Encrypt the blocks

For each block the initialization vector is generated as a random string of 16 bytes with the `random_bytes()` function (denoted as `$iv[$position]`). The block is (by default) AES-256-CTR encrypted with the `$iv[$position]` and the `$filekey` with the `openssl_encrypt()` function and returned as Base64 encoded without zero-padding (denoted as `$encrypted[$position]`).

Sign the blocks

The message authentication key is derived by creating a raw SHA512 hash of `$filekey.$version.$position."a"` with the `hash()` function.

- `$version` is the encrypted value that can be retrieved from the `oc_filecache` table in the database and must not be zero. Take into account that a file in the `oc_filecache` table is identified by its `path` value as well as its `storage` value which references the `numeric_id` field in the `oc_storages` table. Including `$version` into the message authentication key prevents blocks from being swapped between different versions of the same file.
- `$position` is the index of the current block starting at "0" and is appended with "end" for the last block of the file. Including `$position` into the message authentication key prevents blocks from being swapped within the same file. Furthermore, adding "end" to the message authentication key of the last block prevents file truncation attacks.

The signature is then derived by creating a hexademically encoded SHA256-HMAC of `$encrypted[$position]` and the message authentication key with the `hash_hmac()` function (denoted as `$signature[$position]`).

Store the file

The encrypted file is written to the file with the derived `$encrypted[0..$n]`, `$iv[0..$n]` and `$signature[0..$n]` as documented in *File type: file*.

8.9.15 Decryption: read the private key

Read the private key file

The private key is read from the `$username.".privateKey"` file and the values `$encrypted`, `$iv` and `$signature` are parsed as documented in *File type: private key file*.

Derive the decryption key

The salt for the decryption key is derived by creating a raw SHA256 hash of `$uid.$instanceId.$instanceSecret` with the `hash()` function. `$instanceId` can be retrieved as `instanceid` from the `config.php`. `$instanceSecret` can be retrieved as `secret` from the `config.php`.

The decryption key is then derived by creating a raw SHA256-PBKDF2 hash of the password with the salt, 100.000 rounds and (by default) with a target size of 32 bytes (as required for AES-256-CTR) with the `hash_hmac()` function (denoted as `$passphrase`).

The used password depends on the key type:

- master private key: use `secret` from the `config.php`
- public sharing private key: use an empty password
- recovery private key: use the recovery password
- user private key: use the user password

Check the signature

The message authentication key is derived by creating a raw SHA512 hash of `$passphrase.$version.$position.a` with the `hash()` function.

- `$version` is always `"0"`.
- `$position` is always `"0"`.

The signature is then derived by creating a hexadecimally encoded SHA256-HMAC of `$encrypted` and the message authentication key with the `hash_hmac()` function. Only proceed when the derived signature is equal to `$signature` which is checked with the `hash_equals()` function.

Decrypt the private key

The private key is (by default) AES-256-CTR decrypted with the `$iv` and the `$passphrase` with the `openssl_decrypt()` function.

8.9.16 Decryption: read the file key

Read the file key

The encrypted file key is read from the `"fileKey"` file as documented in *File type: file key file*.

Read the envelope key

The encrypted envelope key for the recipient is read from the `$username.".shareKey"` file as documented in *File type: share key file*.

Decrypt/unseal the file key

The encrypted file key is decrypted/unsealed with the `openssl_open()` function with the private key and encrypted envelope key for the recipient (denoted as `$filekey`).

8.9.17 Decryption: decrypt the file

Split the file

The encrypted file is split into a 8192 bytes sized header and one or more 8192 bytes sized blocks. Only the last encrypted block may be shorter. Each block is referenced by its zero-based index within the file (denoted as `$position`). The values `$encrypted[0..$n]`, `$iv[0..$n]` and `$signature[0..$n]` are parsed as documented in *File type: file*.

Check the block signatures

The message authentication key is derived by creating a raw SHA512 hash of `$filekey.$version.$position."a"` with the `hash()` function.

- `$version` is the encrypted value that can be retrieved from the `oc_filecache` table in the database and must not be zero. Take into account that a file in the `oc_filecache` table is identified by its `path` value as well as its `storage` value which references the `numeric_id` field in the `oc_storages` table. Including `$version` into the message authentication key prevents blocks from being swapped between different versions of the same file.
- `$position` is the index of the current block starting at "0" and is appended with "end" for the last block of the file. Including `$position` into the message authentication key prevents blocks from being swapped within the same file. Furthermore, adding "end" to the message authentication key of the last block prevents file truncation attacks.

The signature is then derived by creating a hexadecimally encoded SHA256-HMAC of `$encrypted[$position]` and the message authentication key with the `hash_hmac()` function. Only proceed when the derived signature is equal to `$signature[$position]` which is checked with the `hash_equals()` function.

Decrypt the blocks

Each block is (by default) AES-256-CTR decrypted with the `$iv[$position]` and the `$filekey` with the `openssl_decrypt()` function.

8.9.18 Sources

- [nextcloud-tools repository on GitHub](#)
- [Nextcloud Encryption Configuration documentation](#)
- [Nextcloud Help response concerning the usage of version information](#)
- [Overview of ownCloud Encryption Model](#)
- [Sourcecode: Creation of the Message Authentication Code](#)
- [Sourcecode: Derivation of the Encryption Key](#)
- [Sourcecode: Encryption of the File](#)
- [Sourcecode: Encryption/Sealing of the File Key](#)
- [Sourcecode: Extraction of the Private and Public Key](#)
- [Sourcecode: Generation of the File Key](#)
- [Sourcecode: Generation of the Initialization Vector](#)
- [Sourcecode: Generation of a Key Pair](#)

8.10 Encryption migration

8.10.1 Encryption format

Nextcloud still supports the legacy encryption scheme used for server side encryption where the encrypted files did not contain header information. This may still be used for installations that still have encrypted files from $\leq$ ownCloud 6. Files will be updated to the new encryption format once they are written again. However it is recommended to check if you have to still support this scheme.

Starting with version 20 for new installations the legacy encryption will be off by default. However if you are upgrading there is a migration path to check if you can disable legacy encryption.

Checking for old files

On the command line run:

```
occ encryption:scan:legacy-format
```

The command will tell you if you can remove the legacy encryption mode. If so remove the *encryption.legacy_format_support* from your config.php or set it to *false*.

8.11 Transactional file locking

Nextcloud's Transactional File Locking mechanism locks files to avoid file corruption during normal operation. It performs these functions:

- Operates at a higher level than the filesystem, so you don't need to use a filesystem that supports locking
- Locks parent directories so they cannot be renamed during any activity on files inside the directories
- Releases locks after file transactions are interrupted, for example when a sync client loses the connection during an upload

- Manages locking and releasing locks correctly on shared files during changes from multiple users
- Manages locks correctly on external storage mounts
- Manages encrypted files correctly

What Transactional File locking is not for: it will not prevent multiple users from editing the same document, or give notice that other users are working on the same document. Multiple users can open and edit a file at the same time and Transactional File locking does not prevent this. Rather, it prevents simultaneous file saving.

File locking is enabled by default, using the database locking backend. This places a significant load on your database. Using `memcache.locking` relieves the database load and improves performance. Admins of Nextcloud servers with heavy workloads should install a memcache. (See [Memory caching](#).)

To use a memcache with Transactional File Locking, you must install the Redis server and corresponding PHP module. After installing Redis you must enter a configuration in your `config.php` file like this example:

```
'filelocking.enabled' => true,
'memcache.locking' => '\OC\Memcache\Redis',
'redis' => array(
    'host' => 'localhost',
    'port' => 6379,
    'timeout' => 0.0,
    'password' => '', // Optional, if not defined no password will be used.
),
```

Note: For enhanced security it is recommended to configure Redis to require a password. See <http://redis.io/topics/security> for more information.

If you want to configure Redis to listen on an Unix socket (which is recommended if Redis is running on the same system as Nextcloud) use this example `config.php` configuration:

```
'filelocking.enabled' => true,
'memcache.locking' => '\OC\Memcache\Redis',
'redis' => array(
    'host' => '/var/run/redis/redis.sock',
    'port' => 0,
    'timeout' => 0.0,
),
```

See `config.sample.php` to see configuration examples for Redis, and for all supported memcaches.


If you are on Ubuntu you can follow [this guide](#) for a complete installation from scratch.

Learn more about Redis at [Redis](#). Memcached, the popular distributed memory caching system, is not suitable for the new file locking because it is not designed to store locks, and data can disappear from the cache at any time. Redis is a key-value store, and it guarantees that cached objects are available for as long as they are needed.

8.12 Previews configuration

The Nextcloud thumbnail system generates previews of files for all Nextcloud apps that display files, such as Files and Gallery.

The following image shows some examples of previews of various file types.



	Name ▲		Size	Modified
	background.jpg	 Shared ...	93 KB	an hour ago
	logo.png	 ...	7 KB	seconds ago
	welcome.txt	 Shared ...	< 1 KB	an hour ago
3 files			100 KB	

By default, Nextcloud can generate previews for the following filetypes:

- Images files
- Cover of MP3 files
- Text documents

Note: Technically Nextcloud can also generate the previews of other file types such as PDF, SVG or various office documents. Due to security concerns those providers have been disabled by default and are considered unsupported. While those providers are still available, we discourage enabling them, and they are not documented.

8.12.1 Parameters

Please notice that the Nextcloud preview system comes already with sensible defaults, and therefore it is usually unnecessary to adjust those configuration values.

Disabling previews:

Under certain circumstances, for example if the server has limited resources, you might want to consider disabling the generation of previews. Note that if you do this all previews in all apps are disabled, including the Gallery app, and will display generic icons instead of thumbnails.

Set the configuration option `enable_previews` in `config.php` to `false`:

```
<?php
'enable_previews' => false,
```

Maximum preview size:

There are two configuration options to set the maximum size of a preview.

```
<?php
'preview_max_x' => null,
'preview_max_y' => null,
```

By default, both options are set to null. 'Null' is equal to no limit. Numeric values represent the size in pixels. The following code limits previews to a maximum size of 100×100px:

```
<?php
'preview_max_x' => 100,
'preview_max_y' => 100,
```

'preview_max_x' represents the x-axis and 'preview_max_y' represents the y-axis.

Maximum scale factor:

If a lot of small pictures are stored on the Nextcloud instance and the preview system generates blurry previews, you might want to consider setting a maximum scale factor. By default, pictures are upscaled to 10 times the original size:

```
<?php
'preview_max_scale_factor' => 10,
```

If you want to disable scaling at all, you can set the config value to '1':

```
<?php
'preview_max_scale_factor' => 1,
```

If you want to disable the maximum scaling factor, you can set the config value to 'null':

```
<?php
'preview_max_scale_factor' => null,
```

JPEG quality setting:

Default JPEG quality setting for preview images is '90'. Change this with:

```
occ config:app:set preview jpeg_quality --value="60"
```

8.13 Controlling file versions and aging

The Versions app (files_versions) expires old file versions automatically to ensure that users don't exceed their storage quotas. This is the default pattern used to delete old versions:

- For the first second we keep one version
- For the first 10 seconds Nextcloud keeps one version every 2 seconds
- For the first minute Nextcloud keeps one version every 10 seconds
- For the first hour Nextcloud keeps one version every minute

- For the first 24 hours Nextcloud keeps one version every hour
- For the first 30 days Nextcloud keeps one version every day
- After the first 30 days Nextcloud keeps one version every week

The versions are adjusted along this pattern every time a new version is created.

The Versions app never uses more than 50% of the user's currently available free space. If the stored versions exceed this limit, Nextcloud deletes the oldest file versions until it meets the disk space limit again.

You may alter the default pattern in `config.php`. The default setting is `auto`, which sets the default pattern:

```
'versions_retention_obligation' => 'auto',
```

Additional options are:

- **D, auto** Keep versions at least for D days, apply expiration rules to all versions that are older than D days
- **auto, D** Delete all versions that are older than D days automatically, delete other versions according to expiration rules
- **D1, D2** Keep versions for at least D1 days and delete when they exceed D2 days.
- **disabled** Disable the Versions app; no old file versions will be deleted.

8.13.1 Background job

To delete expired versions a background jobs runs every 30 minutes. It's possible to deactivate the background job and setup a (system) cron to expire the versions via occ.

Deactivate background job: `occ config:app:set --value=no files_versions background_job_expire_versions`

Activate background job: `occ config:app:delete files_versions background_job_expire_versions`

Expire versions: `occ versions:expire` or `occ versions:expire --quiet` (without the progress bar)

FILE WORKFLOWS

9.1 Files access control

Nextcloud's File Access Control app enables administrators to create and manage a set of rule groups. Each of the rule groups consists of one or more rules. If all rules of a group hold true, the group matches the request and access is being denied. The rules criteria range from IP address, to user groups, collaborative tags and *some more*.

9.1.1 Denied access

If access to a file has been denied for a user, the user can not:

- Create/upload the file
- Modify the files
- Delete the file
- Download the file
- Synchronize the file with clients, such as the Nextcloud desktop and mobile clients

9.1.2 Examples

After installing the File Access Control app as described in *Apps management* navigate to the configuration and locate the File Access Control settings.

When ☒ **File is accessed**

and

User group membership

is member of

Support

and

Request time

between

17:00

09:00

Europe/Berlin

Add a new filter

→  Block access to a file

Delete Active

When ☒ **File is accessed**

and

Request remote address

matches IPv4

192.168.1.1/16

and

User group membership

is member of

Internal testers

Add a new filter

→  Block access to a file

Delete Active

The first rule group **Support only 9-5** denies any access to files for users of the Support user group, between 5pm and 9am.

The second rule group **Internal testing** prevents users of the Internal testers group to access files from outside of the local network.

9.1.3 Denying access to folders

The easiest way to block access to a folder, is to use a collaborative tag. As mentioned in the [Available rules](#) section below, either the file itself or one of the parents needs to have the given tag assigned.

So you just need to assign the tag to the folder or file, and then block the tag with a rule group. The check is independent of the user's permissions for the tag. Therefore restricted and invisible tags are recommended, otherwise a user could remove and reassign the tag.

This example blocks access to any folder with the tag **Confidential**.

When **File is accessed**

and File system tag is tagged with Confidential (restricted)

and User group membership is member of Management

[Add a new filter](#)

→  Block access to a file

[Delete](#) [✓ Active](#)

9.1.4 Prevent uploading of specific files

It's possible to prevent specific files from being uploaded to Nextcloud. You simply need to define a rule based on the mimetype and our powerful access control engine will block any attempt to upload the file. The safest way to define the rule is to use a regular expression, as it will help you cover all the known media types used for the type of file you're trying to block.

The following example prevents zip files from being uploaded by using the regular expression: `/^application\/(zip|x-zip-compressed)$/i`

When **File is accessed**

and File MIME type matches  Custom mimetype

`/^application\/(zip|x-zip-compressed)$/i`

[Add a new filter](#)

→  Block access to a file

[Delete](#) [✓ Active](#)

9.1.5 Common misconfigurations

Blocking user groups

When trying to deny access to a group of users, make sure that sharing does not allow them to create a way back in. When users are able to create a public link, the users can log themselves out and visit their own public link to access the files. Since at this point they are no user and therefore no member of the blocked group, they will be able to read and change the file.

The recommended work around is to create the same rule again, and deny access for all users that are not member of a group, that contains all users of your installation.

External storage

While access to files in external storages is not possible via Nextcloud, users that have direct access to the external storage, can of course change files there directly. Therefore it is recommended to disable the `Allow users to mount external storage` option, when trying to completely lock out users.

9.1.6 Available rules

All rules can also be inverted (from `is` to `is not`) using the operator option.

- **File collaborative tag:** Either the file itself, or any of the file owner's parent folders needs to be tagged with the tag.

Note: Tags used in access control rules should be restricted tags, otherwise any user can remove the tag to access the file again. The best way to do this is with the *Automated tagging of files*.

- **File MIME type:** The MIME type of the file, e.g. `text/plain` for a text file or `http/unix-directory` for a folder.

Note: see `mimetypealiases.dist.json` for a full list of possible MIME types.

- **File name:** The name of the file (`is` and `is not` are case-insensitive)
- **File size:** The size of the file (*Only available on upload*)
- **Request remote address:** An IP range (either v4 or v6) for the accessing user
- **Request time:** Time span and timezone when the request happens
- **Request URL:** The URL which requests the file. (*This is the URL the file is served from, not the URL the user is currently looking at.*)
- **Request user agent:** The user agent of the users browser or client. Nextcloud desktop, Android and iOS clients are available as preconfigured options.
- **User group membership:** Whether the user is a member of the given group.

9.2 Automated tagging of files

Nextcloud's Files Automated Tagging app allows to assign collaborative tags to files and folders based on rules, similar to *Files access control*.

9.2.1 Assigning restricted and invisible tags

The main functionality of this app is to allow users to indirectly assign restricted and invisible tags to files they upload. This is especially useful for retention and *Files access control*, so people that got the files shared can not remove the tag to stop the retention or allow access against the owners will.

9.2.2 Example

After installing the Files automated tagging app as described in *Apps management* navigate to the configuration and locate the Workflow settings.

When **File is accessed**

and File system tag is tagged with Protected content

Add a new filter

→ **Automated tagging**
Automated tagging of files

Protected file (restricted)

Delete Active

In the example you can see a simple rule with only one condition. It will tag all files with the restricted tag Protected file that are uploaded into a folder that is tagged with Protected content. No user can remove the tag Protected file and therefor access control and retention both work fine without users being able to work around them.

In this case folder will be also tagged with tag Protected file, to avoid this, simply modify the rule to exclude Directory httpd/unix-directory from it.

When **File is accessed**

and File system tag is tagged with Protected content

and File MIME type is not Custom mimetype

httpd/unix-directory

Add a new filter

→ **Automated tagging**
Automated tagging of files

Protected file (restricted)

Cancel Save

9.2.3 Available rules

The available rules can be seen in the access control section: [Available rules](#).

9.2.4 Executing actions

It is possible to execute actions like ``convert to PDF`` based on assigned tags. Nextcloud GmbH assists customers in this with hands-on help and documentation on our [customer portal](#).

9.3 Retention of files

Nextcloud's Files Retention app allows to automatically delete files that are tagged with a collaborative tag and have a certain age.

9.3.1 Example

After installing the Retention app as described in [Apps management](#) navigate to the configuration and locate the Workflow settings.

File retention

Define if files tagged with a specific tag should be deleted automatically after some time. This is useful for confidential documents.

Tag	Retention Time	
Temporary file	14 days	
Select tag... 10 Days Create ☐ Notify users a day before retention will delete a file		

The rule from the example will delete all files tagged with `Temporary file` after 14 days.

While creating a rule you can use the “Notify users a day before retention will delete a file” option to make sure the users will get a notification before a file gets deleted.

9.3.2 Common misconfigurations

Public collaborative tag

Similar to *Files access control* retention should use **restricted** or **invisible** tags. Otherwise any user can remove the tag and the file is not removed after the given period. Use *Automated tagging of files* to assign such tags to newly uploaded files.

File age

Currently retention is based on the creation date of the file. The sync client sends the **original** creation date to the server, while uploading through the web interface will create a new file with a **new** creation date. We hope to be able to add a `upload_date` to the filesystem soon, which would make more sense. Until then this potentially unexpected behavior has to be taken into account.

GROUPWARE

10.1 Calendar

10.1.1 Invitations

Nextcloud can send invitations for event attendees if this option is activated. Be sure to have configured the email server first so that the invitations go through. See [Email](#).

You must also make sure the “Send invitations to attendees” setting is activated in the admin setting groupware section for the emails to be sent.

10.1.2 Birthday calendar

Contacts that have a birthday date filled are automatically added as events to a special Birthday calendar. If you deactivate this option, all users will no longer have this calendar.

When activating this option, users birthday calendars won’t be available right away because they need to be generated by a background task. See [Using the occ command](#) section Dav commands.

10.1.3 Reminder notifications

Nextcloud handles sending notifications for events.

Nextcloud currently handles two types of reminder notifications: Build-in Nextcloud notifications and email notifications. For the emails to be send, you’ll need a configured email server. See [Email](#).

Make sure the “Send notifications for events” and the “Enable notifications for events via push” are activated in the admin setting groupware section for this feature to work.

Background jobs

Running background jobs can be an expensive task when there are a large number of events, reminders, event sharees and attendees. However, this needs to happen often enough so that the notifications are sent on time. To accomplish this you should use a dedicated occ command that runs more often than the standard cron system:

```
# crontab -u www-data -e
*/5 * * * * php -f /var/www/nextcloud/occ dav:send-event-reminders
```

See [Using the occ command](#) section Dav commands.

You’ll also need to change the sending mode from background-job to occ:

```
php occ config:app:set dav sendEventRemindersMode --value occ
```

If you don't use this dedicated command, the reminders will just be sent as soon as possible when the background jobs run.

10.1.4 FreeBusy

When logged-in, Nextcloud can return FreeBusy information for all users of the instance, to know when they are available so that you can schedule an event at the right time. If you don't wish for users to have this capability, you can disable FreeBusy for the whole instance with the following setting:

```
php occ config:app:set dav disableFreeBusy --value yes
```

10.1.5 Subscriptions

Refresh rate

Calendar subscriptions are cached on server and refreshed periodically. The default refresh rate is one week, unless the subscription itself tells otherwise.

To set up a different default refresh rate, change the `calendarSubscriptionRefreshRate` option:

```
php occ config:app:set dav calendarSubscriptionRefreshRate --value "P1D"
```

Where the value is a [DateInterval](#), for instance with the above command all of the Nextcloud instance's calendars would be refreshed every day.

Allow subscriptions on local network

Because of security issues, Nextcloud forbids subscriptions from local network hosts. If you need to allow this, change the following parameter to:

```
php occ config:app:set dav webcalAllowLocalAccess --value yes
```

DATABASE CONFIGURATION

11.1 Converting database type

You can convert a SQLite database to a better performing MySQL, MariaDB or PostgreSQL database with the Nextcloud command line tool. SQLite is good for testing and simple single-user Nextcloud servers, but it does not scale for multiple-user production users.

11.1.1 Run the conversion

First set up the new database, here called “new_db_name”. In Nextcloud root folder call

```
php occ db:convert-type [options] type username hostname database
```

The Options

- `--port="3306"` the database port (optional)
- `--password="mysql_user_password"` password for the new database. If omitted the tool will ask you (optional)
- `--clear-schema` clear schema (optional)
- `--all-apps` by default, tables for enabled apps are converted, use to convert also tables of deactivated apps (optional)
- `-n`, `--no-interaction` do not ask any interactive question

Note: The converter searches for apps in your configured app folders and uses the schema definitions in the apps to create the new table. So tables of removed apps will not be converted even with option `--all-apps`

For example

```
php occ db:convert-type --all-apps mysql oc_mysql_user 127.0.0.1 new_db_name
```

To successfully proceed with the conversion, you must type `yes` when prompted with the question `Continue with the conversion?`

On success the converter will automatically configure the new database in your Nextcloud config `config.php`.

11.1.2 Inconvertible tables

If you updated your Nextcloud instance, there might be remnants of old tables which are not used any more. The updater will tell you which ones these are.

The following tables will **not** be converted:
oc_permissions

...

You can ignore these tables. Here is a list of known old tables:

- oc_calendar_calendars
- oc_calendar_objects
- oc_calendar_share_calendar
- oc_calendar_share_event
- oc_fscache
- oc_log
- oc_media_albums
- oc_media_artists
- oc_media_sessions
- oc_media_songs
- oc_media_users
- oc_permissions
- oc_privatedata - this table was later added again by the app *privatedata* (<https://apps.nextcloud.com/apps/privatedata>) and is safe to be removed if that app is not enabled
- oc_queuedtasks
- oc_sharing

11.2 Database configuration

Nextcloud requires a database in which administrative data is stored. The following databases are currently supported:

- MySQL / MariaDB
- PostgreSQL
- Oracle

The MySQL or MariaDB databases are the recommended database engines.

11.2.1 Requirements

Choosing to use MySQL / MariaDB, PostgreSQL, or Oracle as your database requires that you install and set up the server software first.

Note: The steps for configuring a third party database are beyond the scope of this document. Please refer to the documentation for your specific database choice for instructions.

Database “READ COMMITTED” transaction isolation level

As discussed above Nextcloud is using the TRANSACTION_READ_COMMITTED transaction isolation level. Some database configurations are enforcing other transaction isolation levels. To avoid data loss under high load scenarios (e.g. by using the sync client with many clients/users and many parallel operations) you need to configure the transaction isolation level accordingly. Please refer to the [MySQL manual](#) for detailed information.

11.2.2 Parameters

For setting up Nextcloud to use any database, use the instructions in *Installation wizard*. You should not have to edit the respective values in the config/config.php. However, in special cases (for example, if you want to connect your Nextcloud instance to a database created by a previous installation of Nextcloud), some modification might be required.

Configuring a MySQL or MariaDB database

If you decide to use a MySQL or MariaDB database, ensure the following:

- The transaction isolation level is set to “READ-COMMITTED” in your MariaDB server configuration /etc/mysql/my.cnf to persist even after a restart of your database server.

Verify the **transaction_isolation** and **binlog_format**:

```
[mysqld]
...
transaction_isolation = READ-COMMITTED
binlog_format = ROW
...
```

Your /etc/mysql/my.cnf could look like this:

```
[server]
skip_name_resolve = 1
innodb_buffer_pool_size = 128M
innodb_buffer_pool_instances = 1
innodb_flush_log_at_trx_commit = 2
innodb_log_buffer_size = 32M
innodb_max_dirty_pages_pct = 90
query_cache_type = 1
query_cache_limit = 2M
query_cache_min_res_unit = 2k
query_cache_size = 64M
tmp_table_size= 64M
max_heap_table_size= 64M
```

(continues on next page)

(continued from previous page)

```

slow_query_log = 1
slow_query_log_file = /var/log/mysql/slow.log
long_query_time = 1

[client-server]
!includedir /etc/mysql/conf.d/
!includedir /etc/mysql/mariadb.conf.d/

[client]
default-character-set = utf8mb4

[mysqld]
character_set_server = utf8mb4
collation_server = utf8mb4_general_ci
transaction_isolation = READ-COMMITTED
binlog_format = ROW
innodb_large_prefix=on
innodb_file_format=barracuda
innodb_file_per_table=1

```

Please refer to the [page in the MySQL manual](#).

- That you have installed and enabled the pdo_mysql extension in PHP
- That the **mysql.default_socket** points to the correct socket (if the database runs on the same server as Nextcloud).

Note: MariaDB is backwards compatible with MySQL. All instructions work for both. You will not need to replace mysql with anything.

The PHP configuration in `/etc/php7/conf.d/mysql.ini` could look like this:

```

# configuration for PHP MySQL module
extension=pdo_mysql.so

[mysql]
mysql.allow_local_infile=On
mysql.allow_persistent=On
mysql.cache_size=20000
mysql.max_persistent=-1
mysql.max_links=-1
mysql.default_port=
mysql.default_socket=/var/lib/mysql/mysql.sock # Debian squeeze: /var/run/mysqld/mysqld.
↪ sock
mysql.default_host=
mysql.default_user=
mysql.default_password=
mysql.connect_timeout=60
mysql.trace_mode=Off

```

Now you need to create a database user and the database itself by using the MySQL command line interface. The database tables will be created by Nextcloud when you login for the first time.

To start the MySQL command line mode use:

```
mysql -uroot -p
```

Then a **mysql>** or **MariaDB [root]>** prompt will appear. Now enter the following lines and confirm them with the enter key:

```
CREATE USER 'username'@'localhost' IDENTIFIED BY 'password';
CREATE DATABASE IF NOT EXISTS nextcloud CHARACTER SET utf8mb4 COLLATE utf8mb4_general_ci;
GRANT ALL PRIVILEGES ON nextcloud.* TO 'username'@'localhost';
FLUSH privileges;
```

You can quit the prompt by entering:

```
quit;
```

A Nextcloud instance configured with MySQL would contain the hostname on which the database is running, a valid username and password to access it, and the name of the database. The `config/config.php` as created by the *Installation wizard* would therefore contain entries like this:

```
<?php

"dbtype"          => "mysql",
"dbname"          => "nextcloud",
"dbuser"          => "username",
"dbpassword"      => "password",
"dbhost"          => "localhost",
"dbtableprefix"  => "oc_",
```

In case of UTF8MB4 you will also find:

```
"mysql.utf8mb4" => true,
```

SSL for MySQL Database

Enabling SSL is only necessary if your database does not reside on the same server as your Nextcloud instance. If you do not connect over localhost and need to allow remote connections then you should enable SSL. This just covers the SSL database configuration on the Nextcloud server. First you need to configure your database server accordingly.

```
'dbdriveroptions' => [
    \PDO::MYSQL_ATTR_SSL_KEY => '../ssl-key.pem',
    \PDO::MYSQL_ATTR_SSL_CERT => '../ssl-cert.pem',
    \PDO::MYSQL_ATTR_SSL_CA => '../ca-cert.pem',
    \PDO::MYSQL_ATTR_SSL_VERIFY_SERVER_CERT => true,
],
```

Adjust the paths to the pem files for your environment.

PostgreSQL database

If you decide to use a PostgreSQL database make sure that you have installed and enabled the PostgreSQL extension in PHP. The PHP configuration in `/etc/php7/conf.d/pgsql.ini` could look like this:

```
# configuration for PHP PostgreSQL module
extension=pdo_pgsql.so
extension=pgsql.so

[PostgreSQL]
pgsql.allow_persistent = On
pgsql.auto_reset_persistent = Off
pgsql.max_persistent = -1
pgsql.max_links = -1
pgsql.ignore_notice = 0
pgsql.log_notice = 0
```

The default configuration for PostgreSQL (at least in Ubuntu 14.04) is to use the peer authentication method. Check `/etc/postgresql/9.3/main/pg_hba.conf` to find out which authentication method is used in your setup. To start the postgres command line mode use:

```
sudo -u postgres psql -d template1
```

Then a **template1=#** prompt will appear. Now enter the following lines and confirm them with the enter key:

```
CREATE USER username CREATEDB;
CREATE DATABASE nextcloud OWNER username;
```

You can quit the prompt by entering:

```
\q
```

A Nextcloud instance configured with PostgreSQL would contain the path to the socket on which the database is running as the hostname, the system username the PHP process is using, and an empty password to access it, and the name of the database. The `config/config.php` as created by the *Installation wizard* would therefore contain entries like this:

```
<?php

"dbtype"          => "pgsql",
"dbname"          => "nextcloud",
"dbuser"          => "username",
"dbpassword"      => "",
"dbhost"          => "/var/run/postgresql",
"dbtableprefix"  => "oc_",
```

Note: The host actually points to the socket that is used to connect to the database. Using localhost here will not work if postgresQL is configured to use peer authentication. Also note that no password is specified, because this authentication method doesn't use a password.

If you use another authentication method (not peer), you'll need to use the following steps to get the database setup: Now you need to create a database user and the database itself by using the PostgreSQL command line interface. The database tables will be created by Nextcloud when you login for the first time.

To start the postgres command line mode use:

```
psql -hlocalhost -Upostgres
```

Then a **postgres=#** prompt will appear. Now enter the following lines and confirm them with the enter key:

```
CREATE USER username WITH PASSWORD 'password';
CREATE DATABASE nextcloud TEMPLATE template0 ENCODING 'UNICODE';
ALTER DATABASE nextcloud OWNER TO username;
GRANT ALL PRIVILEGES ON DATABASE nextcloud TO username;
```

You can quit the prompt by entering:

```
\q
```

A Nextcloud instance configured with PostgreSQL would contain the hostname on which the database is running, a valid username and password to access it, and the name of the database. The `config/config.php` as created by the *Installation wizard* would therefore contain entries like this:

```
<?php

"dbtype"          => "pgsql",
"dbname"          => "nextcloud",
"dbuser"          => "username",
"dbpassword"      => "password",
"dbhost"          => "localhost",
"dbtableprefix"  => "oc_",
```

11.2.3 Troubleshooting

How to work around “general error: 2006 MySQL server has gone away”

The database request takes too long and therefore the MySQL server times out. It’s also possible that the server is dropping a packet that is too large. Please refer to the manual of your database for how to raise the configuration options `wait_timeout` and/or `max_allowed_packet`.

Some shared hosters are not allowing the access to these config options. For such systems Nextcloud is providing a `dbdriveroptions` configuration option within your `config/config.php` where you can pass such options to the database driver. Please refer to *Configuration Parameters* for an example.

How can I find out if my MySQL/PostgreSQL server is reachable?

To check the server’s network availability, use the ping command on the server’s host name (db.server.com in this example):

```
ping db.server.com
```

```
PING db.server.com (ip-address) 56(84) bytes of data.
64 bytes from your-server.local.lan (192.168.1.10): icmp_req=1 ttl=64 time=3.64 ms
64 bytes from your-server.local.lan (192.168.1.10): icmp_req=2 ttl=64 time=0.055 ms
64 bytes from your-server.local.lan (192.168.1.10): icmp_req=3 ttl=64 time=0.062 ms
```

For a more detailed check whether the access to the database server software itself works correctly, see the next question.

How can I find out if a created user can access a database?

The easiest way to test if a database is accessible is by starting the command line interface:

MySQL:

Assuming the database server is installed on the same system you're running the command from, use:

```
mysql -uUSERNAME -p
```

To access a MySQL installation on a different machine, add the `-h` option with the respective host name:

```
mysql -uUSERNAME -p -h HOSTNAME
```

```
mysql> SHOW VARIABLES LIKE "version";
+-----+
| Variable_name | Value |
+-----+
| version      | 8.0.22 |
+-----+
1 row in set (0.00 sec)
mysql> quit
```

PostgreSQL:

Assuming the database server is installed on the same system you're running the command from, use:

```
psql -Uusername -dnextcloud
```

To access a PostgreSQL installation on a different machine, add the `-h` option with the respective host name:

```
psql -Uusername -dnextcloud -h HOSTNAME
```

```
postgres=# SELECT version();
PostgreSQL 8.4.12 on i686-pc-linux-gnu, compiled by GCC gcc (GCC) 4.1.3 20080704,
↳ (prerelease), 32-bit
(1 row)
postgres=# \q
```

Useful SQL commands

Show Database Users:

```
MySQL      : SELECT User,Host FROM mysql.user;
PostgreSQL: SELECT * FROM pg_user;
```

Show available Databases:

```
MySQL      : SHOW DATABASES;
PostgreSQL: \l
```

Show Nextcloud Tables in Database:

```
MySQL      : USE nextcloud; SHOW TABLES;
PostgreSQL: \c nextcloud; \d
```

Quit Database:

```
MySQL      : quit
PostgreSQL: \q
```

11.3 Enabling MySQL 4-byte support

Note: Be sure to backup your database before performing this database upgrade.

In order to use Emojis (textbased smilies) on your Nextcloud server with a MySQL database, the installation needs to be tweaked a bit.

Note: This manual only covers MySQL 8 or newer and MariaDB 10.3 or newer. If you use an older version, please check an older version of the documentation

1. Make sure the following InnoDB settings are set on your MySQL server:

```
[mysqld]
innodb_file_per_table=1
```

Note:

```
mysql> show variables like 'innodb_file_per_table';
+-----+-----+
| Variable_name | Value |
+-----+-----+
| innodb_file_per_table | ON    |
+-----+-----+
1 row in set (0.00 sec)
```

2. Open a shell, change dir (adjust `/var/www/nextcloud` to your nextcloud location if needed), and put your nextcloud instance in maintenance mode, if it isn't already:

```
$ cd /var/www/nextcloud
$ sudo -u www-data php occ maintenance:mode --on
```

3. Restart the MySQL server in case you changed the configuration in step 1.
4. Change your databases character set and collation:

```
ALTER DATABASE nextcloud CHARACTER SET utf8mb4 COLLATE utf8mb4_general_ci;
```

5. Set the `mysql.utf8mb4` config to true in your `config.php`:

```
$ sudo -u www-data php occ config:system:set mysql.utf8mb4 --type boolean --value=
→ "true"
```

6. Convert all existing tables to the new collation by running the repair step:

```
$ sudo -u www-data php occ maintenance:repair
```

Note: This will also change the *ROW_FORMAT* to *COMPRESSED* for your tables, to make sure the used database storage size is not getting out of hand.

7. Disable maintenance mode:

```
$ sudo -u www-data php occ maintenance:mode --off
```

Now you should be able to use Emojis in your file names, calendar events, comments and many more.

Note: Also make sure your backup strategy still work. If you use `mysqldump` make sure to add the `--default-character-set=utf8mb4` option. Otherwise your backups are broken and restoring them will result in ? instead of the emojis, making files inaccessible.

11.4 BigInt (64bit) identifiers

Nextcloud uses big integers to store identifiers and auto-increment keys in the database. Because changing columns on huge tables can take quite a while (up to hours or days) depending on the number of files in the Nextcloud instance, this migration on the filecache and activity table has to be triggered manually by a console command.

The command can safely be executed. It will show a success message when there is nothing to do:

```
sudo -u www-data php occ db:convert-filecache-bigint
All tables already up to date!
```

or otherwise ask for confirmation, before performing the heavy actions:

```
sudo -u www-data php occ db:convert-filecache-bigint
This can take up to hours, depending on the number of files in your instance!
Continue with the conversion (y/n)? [n]
```

to suppress the confirmation message append `--no-interaction` to the argument list:

```
sudo -u www-data php occ db:convert-filecache-bigint --no-interaction
```

Note: Similar to a normal update, you should shutdown your Apache or nginx server or enable maintenance mode before running the command to avoid issues with your sync clients.

MIMETYPES MANAGEMENT

12.1 Mimetype aliases

Nextcloud allows you to create aliases for mimetypes, so that you can display custom icons for files. For example, you might want a nice audio icon for audio files instead of the default file icon.

By default Nextcloud is distributed with `nextcloud/resources/config/mimetypealiases.dist.json`. Do not modify this file, as it will be replaced when Nextcloud is updated. Instead, create your own `nextcloud/config/mimetypealiases.json` file with your custom aliases. Use the same syntax as in `nextcloud/resources/config/mimetypealiases.dist.json`.

Once you have made changes to your `mimetypealiases.json`, use the `occ` command to propagate the changes through the system. This example is for Ubuntu Linux:

```
$ sudo -u www-data php occ maintenance:mimetype:update-js
```

See *Using the occ command* to learn more about `occ`.

Some common mimetypes that may be useful in creating aliases are:

image Generic image

image/vector Vector image

audio Generic audio file

x-office/document Word processed document

x-office/spreadsheet Spreadsheet

x-office/presentation Presentation

text Generic text document

text/code Source code

12.2 Mimetype mapping

Nextcloud allows administrators to specify the mapping of a file extension to a mimetype. For example files ending in `mp3` map to `audio/mpeg`. Which then in turn allows Nextcloud to show the audio icon.

By default Nextcloud comes with `mimetypermapping.dist.json`. This is a simple json array. Administrators should not update this file as it will get replaced on upgrades of Nextcloud. Instead the `mimetypermapping.json` should be created and modified, this file has precedence over the shipped file.

12.3 Icon retrieval

When an icon is retrieved for a mimetype, if the full mimetype cannot be found, the search will fallback to looking for the part before the slash. Given a file with the mimetype 'image/my-custom-image', if no icon exists for the full mimetype, the icon for 'image' will be used instead. This allows specialised mimetypes to fallback to generic icons when the relevant icons are unavailable.

MAINTENANCE

13.1 Backup

To backup a Nextcloud installation there are four main things you need to retain:

1. The config folder
2. The data folder
3. The theme folder
4. The database

13.1.1 Maintenance mode

`maintenance:mode` locks the sessions of logged-in users and prevents new logins in order to prevent inconsistencies of your data. You must run `occ` as the HTTP user, like this example on Ubuntu Linux:

```
$ sudo -u www-data php occ maintenance:mode --on
```

You may also put your server into this mode by editing `config/config.php`. Change `"maintenance" => false` to `"maintenance" => true`:

```
<?php  
  
"maintenance" => true,
```

Don't forget to change it back to `false` when you are finished.

13.1.2 Backup folders

Simply copy your config, data and theme folders (or even your whole Nextcloud install and data folder) to a place outside of your Nextcloud environment. You could use this command:

```
rsync -Aavx nextcloud/ nextcloud-dirbkp_`date +"%Y%m%d"` /
```

13.1.3 Backup database

Warning: Before restoring a backup see *Restoring backup*

MySQL/MariaDB

MySQL or MariaDB, which is a drop-in MySQL replacement, is the recommended database engine. To backup MySQL/MariaDB:

```
mysqldump --single-transaction -h [server] -u [username] -p[password] [db_name] >↵  
↵nextcloud-sqlbkp_`date +%Y%m%d``.bak
```

If you use enabled MySQL/MariaDB 4-byte support (*Enabling MySQL 4-byte support*, needed for emoji), you will need to add `--default-character-set=utf8mb4` like this:

```
mysqldump --single-transaction --default-character-set=utf8mb4 -h [server] -u [username]↵  
↵-p[password] [db_name] > nextcloud-sqlbkp_`date +%Y%m%d``.bak
```

SQLite

```
sqlite3 data/owncloud.db .dump > nextcloud-sqlbkp_`date +%Y%m%d``.bak
```

PostgreSQL

```
PGPASSWORD="password" pg_dump [db_name] -h [server] -U [username] -f nextcloud-sqlbkp_↵  
↵`date +%Y%m%d``.bak
```

13.2 Restoring backup

To restore a Nextcloud installation there are four main things you need to restore:

1. The configuration directory
2. The data directory
3. The database
4. The theme directory

Note: You must have both the database and data directory. You cannot complete restoration unless you have both of these.

When you have completed your restoration, also make sure to run the *maintenance:data-fingerprint* command afterwards, to ensure your sync clients can recover from the restored backup.

13.2.1 Restore folders

Note: This guide assumes that your previous backup is called “nextcloud-dirbkp”

Simply copy your configuration and data folder (or even your whole Nextcloud install and data folder) to your Nextcloud environment. You could use this command:

```
rsync -Aax nextcloud-dirbkp/ nextcloud/
```

13.2.2 Restore database

Warning: Before restoring a backup you need to make sure to delete all existing database tables.

The easiest way to do this is to drop and recreate the database. SQLite does this automatically.

MySQL

MySQL is the recommended database engine. To restore MySQL:

```
mysql -h [server] -u [username] -p[password] -e "DROP DATABASE nextcloud"
mysql -h [server] -u [username] -p[password] -e "CREATE DATABASE nextcloud"
```

If you use UTF8 with multibyte support (e.g. for emojis in filenames), use:

```
mysql -h [server] -u [username] -p[password] -e "DROP DATABASE nextcloud"
mysql -h [server] -u [username] -p[password] -e "CREATE DATABASE nextcloud CHARACTER SET_
↳utf8mb4 COLLATE utf8mb4_general_ci"
```

PostgreSQL

```
PGPASSWORD="password" psql -h [server] -U [username] -d template1 -c "DROP DATABASE \
↳nextcloud\;"
PGPASSWORD="password" psql -h [server] -U [username] -d template1 -c "CREATE DATABASE \
↳nextcloud\;"
```

13.2.3 Restoring

Note: This guide assumes that your previous backup is called “nextcloud-sqlbkp.bak”

MySQL

MySQL is the recommended database engine. To restore MySQL:

```
mysql -h [server] -u [username] -p[password] [db_name] < nextcloud-sqlbkp.bak
```

SQLite

```
rm data/owncloud.db  
sqlite3 data/owncloud.db < nextcloud-sqlbkp.bak
```

PostgreSQL

```
PGPASSWORD="password" psql -h [server] -U [username] -d nextcloud -f nextcloud-sqlbkp.bak
```

13.3 How to upgrade

There are three ways to upgrade your Nextcloud server:

- With the *Updater*.
- *Manually upgrading* with the Nextcloud .tar archive from our [Download page](#).
- *Upgrading* via the snap packages.
- Manually upgrading is also an option for users on shared hosting; download and unpack the Nextcloud tarball to your PC. Delete your existing Nextcloud files, except data/ and config/ files, on your hosting account. Then transfer the new Nextcloud files to your hosting account, again preserving your existing data/ and config/ files.

When an update is available for your Nextcloud server, you will see a notification at the top of your Nextcloud Web interface. When you click the notification it brings you here, to this page.

It is best to keep your Nextcloud server upgraded regularly, and to install all point releases and major releases. Major releases are 18, 19 or 20. Point releases are intermediate releases for each major release. For example 18.0.4 and 19.0.2 are point releases.

Nextcloud must be upgraded step by step:

- Before you can upgrade to the next major release, Nextcloud upgrades to the latest point release.
- Then run the upgrade again to upgrade to the next major release's latest point release.
- **You cannot skip major releases.** Please re-run the upgrade until you have reached the highest available (or applicable) release.
- Example: 18.0.5 -> 18.0.11 -> 19.0.5 -> 20.0.2

Upgrading is disruptive. Your Nextcloud server will be put into maintenance mode, so your users will be locked out until the upgrade is completed. Large installations may take several hours to complete the upgrade. Nevertheless usual upgrade times even for bigger installations are in the range of a few minutes.

Warning: Downgrading is **not supported** and risks corrupting your data! If you want to revert to an older Nextcloud version, make a new, fresh installation and then restore your data from backup. Before doing this, file a support ticket (if you have paid support) or ask for help in the Nextcloud forums to see if your issue can be resolved without downgrading.

13.3.1 Update notifications

Nextcloud has an update notification app, that informs the administrator about the availability of an update. Then you decide which update method to use.




Fig. 1: Figure 1: The top banner is the update notification that is shown on every page, and the Updates section can be found in the admin page

From there the web based updater can be used to fetch this new code. There is also an CLI based updater available, that does exactly the same as the web based updater but on the command line.

13.3.2 Prerequisites

You should always maintain *regular backups* and make a fresh backup before every upgrade.

Then review third-party apps, if you have any, for compatibility with the new Nextcloud release. Any apps that are not developed by Nextcloud show a 3rd party designation. **Install unsupported apps at your own risk.** Then, before the upgrade, all 3rd party apps must be disabled. After the upgrade is complete you may re-enable them.

13.3.3 Maintenance mode

You can put your Nextcloud server into maintenance mode before performing upgrades, or for performing troubleshooting or maintenance. Please see *Using the occ command* to learn how to put your server into the maintenance mode (`maintenance:mode`) or execute repair commands (`maintenance:repair`) with the `occ` command.

The *build-in Updater* does this for you before replacing the existing Nextcloud code with the code of the new Nextcloud version.

`maintenance:mode` locks the sessions of logged-in users and prevents new logins. This is the mode to use for upgrades. You must run `occ` as the HTTP user, like this example on Ubuntu Linux:

```
$ sudo -u www-data php occ maintenance:mode --on
```

You may also put your server into this mode by editing `config/config.php`. Change `"maintenance" => false` to `"maintenance" => true`:

```
<?php

"maintenance" => true,
```

Then change it back to `false` when you are finished.

13.3.4 Manual steps during upgrade

Some operation can be quite time consuming. Therefore we decided not to add them to the normal upgrade process. We recommend to run them manually after the upgrade was completed. Below you find a list of this commands.

Long running migration steps

From time to time we do some changes to the database layout that take a lot of time, but can be executed while Nextcloud stays online. Thus we moved them into a separate command that an administrator can execute on the CLI without the need to lock the instance into maintenance mode (at least for some of them). The instance will also work without those changes applied, but performance is improved significantly by them. There is also always an hint in the setup checks of the admin settings web interface.

Those include for example:

```
$ sudo -u www-data php occ db:add-missing-columns
$ sudo -u www-data php occ db:add-missing-indices
```

13.4 Upgrade via built-in updater

The built-in updater automates many of the steps of upgrading a Nextcloud installation. It is useful for installations that do not have root access, such as shared hosting, for installations with a smaller number of users and data, and it automates updating *manual installations*.

Warning: **Downgrading** is not supported and risks corrupting your data! If you want to revert to an older Nextcloud version, install it from scratch and then restore your data from backup. Before doing this, file a support ticket if you have paid support or ask for help in the Nextcloud forums to see if your issue can be resolved without downgrading.

You should maintain regular backups (see [Backup](#)), and make a backup before every update. The built-in updater does not backup your database or data directory.

13.4.1 What does the updater do?

Note: The updater itself only replaces the existing files with the ones from the version it updates to. The migration steps needs to be executed afterwards. The command line mode provides a way to do this right after the code was successfully replaced.


The built-in updater performs these operations:

- **Check for expected files:** checks if only the expected files of a Nextcloud installation are present, because it turned out that some files that were left in the Nextcloud directory caused side effects that risked the update procedure.
- **Check for write permissions:** checks if all files that need to be writable during the update procedure are actually writable.
- **Enable maintenance mode:** enables the maintenance mode so that no other actions are executed while running the update of the code.
- **Create backup:** creates a backup of the existing code base in `/updater-INSTANCEID/backups/nextcloud-CURRENTVERSION/` inside of the data directory (this does not contain the `/data` directory nor the database).
- **Downloading:** downloads the code in the version it should update to. This is also shown in the web UI before the update is started. This archive is downloaded to `/updater-INSTANCEID/downloads/`.
- **Extracting:** extracts the archive to the same folder.
- **Replace entry points:** replaces all Nextcloud entry points with dummy files so that when those files are replaced all clients still get the proper maintenance mode response. Examples for those endpoints are `index.php`, `remote.php` or `ocs/v1.php`.
- **Delete old files:** deletes all files except the above mentioned entry points, the data and config dir as well as non-shipped apps and themes. (And the updater itself of course)
- **Move new files in place:** moves the files from the extracted archive in place.
- **Keep maintenance mode active?:** asks you if the maintenance mode should be kept active. This allows the admin to use the web based updater but run the actual migration steps (`occ upgrade`) on the command line. If the maintenance mode is kept active command line access is required. To use the web based upgrade page disable the maintenance mode and click the link to get to the upgrade page. (This step is only available in the web based updater.)
- **Done** the update of the code is done and you either need to go to the linked page or to the command line to finish the upgrade by executing the migration steps.


13.4.2 Using the web based updater

Using the built-in updater to update your Nextcloud installation is just a few steps:


1. You should see a notification at the top of any Nextcloud page when there is a new update available. Go to the admin settings page and scroll to the section “Version”. This section has a button to open the updater. This section as well as the update notification is only available if the update notification app is enabled in the apps management.




2. Click the button “Open updater”.




3. Verify the information that is shown and click the button “Start update” to start the update.




4. In case an error happens or the check failed the updater stops processing and gives feedback. You can now try to solve the problem and click the “Retry update” button. This will continue the update and re-run the failed step. It will not re-run the previous succeeded steps.



5. In case you close the updater, before it finished you can just open the updater page again and proceed at the last succeeded step. Closing the web page will still execute the running step but will not continue with the next one, because this is triggered by the open updater page.




6. Once all steps are executed the updater will ask you a final question: “Keep maintenance mode active?”. This allows you to use either the web based upgrade page or the command line based upgrade procedure (`occ upgrade`). Command line access is required if the maintenance mode is kept active.




7. Done. You now can continue either to the web based upgrade page or run `occ upgrade`. The two examples “Web based upgrade” and “Command line based upgrade” shows how the screens then look like.

Web based upgrade


This is how the web based update would continue:





Command line based upgrade

This is how the command line based update would continue:



```
$ sudo -u www-data php ./occ upgrade
Nextcloud or one of the apps require upgrade - only a limited number of commands are
↪ available
You may use your browser or the occ upgrade command to do the upgrade
Set log level to debug
Updating database schema
Updated database
Updating <files_pdfviewer> ...
Updated <files_pdfviewer> to 1.1.1
Updating <gallery> ...
Updated <gallery> to 17.0.0
Updating <activity> ...
Updated <activity> to 2.5.2
Updating <comments> ...
Updated <comments> to 1.2.0
Updating <theming> ...
Updated <theming> to 1.3.0
Starting code integrity check...
Finished code integrity check
Update successful
Maintenance mode is kept active
Reset log level
```


13.4.3 Using the command line based updater

The command line based updater works in the exact same way the web based updater works. The steps and checks are the very same.

Warning: APCu is disabled by default on CLI which could cause issues with nextcloud's command line based updater. Please make sure you set the `apc.enable_cli` to 1 on your `php.ini` config file or append `--define apc.enable_cli=1` to the command line based updater call (like `sudo -u www-data php --define apc.enable_cli=1 /var/www/nextcloud/updater/updater.phar`).

The steps are basically the same as for the web based updater:

1. You should see a notification at the top of any Nextcloud page when there is a new update available. Go to the admin settings page and scroll to the section "Version". This section has a button to open the updater. This section as well as the update notification is only available if the update notification app is enabled in the apps management.



2. Instead of clicking that button you can now invoke the command line based updater by going into the `updater/` directory in the Nextcloud directory and executing the `updater.phar` as the web server user. (i.e. `sudo -u www-data php /var/www/nextcloud/updater/updater.phar`)

```
Nextcloud Updater - version: 1.0.3

Current version is 11.0.1.

Update to Nextcloud 12.0.0 Beta 2 available. (channel: "beta")
Following file will be downloaded automatically: https://download.nextcloud.com/server/prereleases/nextcloud-12.0.0beta2.zip

Steps that will be executed:
[ ] Check for expected files
[ ] Check for write permissions
[ ] Enable maintenance mode
[ ] Create backup
[ ] Downloading
[ ] Extracting
[ ] Replace entry points
[ ] Delete old files
[ ] Move new files in place
[ ] Done

Start update? [y/N] █
```

3. Verify the information that is shown and enter “Y” to start the update.

```
Nextcloud Updater - version: 1.0.3

Current version is 11.0.1.

Update to Nextcloud 12.0.0 Beta 2 available. (channel: "beta")
Following file will be downloaded automatically: https://download.nextcloud.com/server/prereleases/nextcloud-12.0.0beta2.zip

Steps that will be executed:
[ ] Check for expected files
[ ] Check for write permissions
[ ] Enable maintenance mode
[ ] Create backup
[ ] Downloading
[ ] Extracting
[ ] Replace entry points
[ ] Delete old files
[ ] Move new files in place
[ ] Done

Start update? [y/N] y

Info: Pressing Ctrl-C will finish the currently running step and then stops the updater.

[✓] Check for expected files
[ ] Check for write permissions ...█

Nextcloud Updater - version: 1.0.3

Current version is 11.0.1.

Update to Nextcloud 12.0.0 Beta 2 available. (channel: "beta")
Following file will be downloaded automatically: https://download.nextcloud.com/server/prereleases/nextcloud-12.0.0beta2.zip

Steps that will be executed:
[ ] Check for expected files
[ ] Check for write permissions
[ ] Enable maintenance mode
[ ] Create backup
[ ] Downloading
[ ] Extracting
[ ] Replace entry points
[ ] Delete old files
[ ] Move new files in place
[ ] Done

Start update? [y/N] y

Info: Pressing Ctrl-C will finish the currently running step and then stops the updater.

[✗] Check for expected files failed
The following extra files have been found:
  unexpectedFile.php

Update failed. To resume or retry just execute the updater again.
```

4. In case an error happens or the check failed the updater stops processing and gives feedback. You can now try to solve the problem and re-run the updater command. This will continue the update and re-run the failed step. It will not re-run the previous succeeded steps.

Nextcloud Updater – version: 1.0.3

Current version is 11.0.1.

Update to Nextcloud 12.0.0 Beta 2 available. (channel: "beta")
Following file will be downloaded automatically: <https://download.nextcloud.com/server/prereleases/nextcloud-12.0.0beta2.zip>

Steps that will be executed:

```
[✓] Check for expected files
[ ] Check for write permissions
[ ] Enable maintenance mode
[ ] Create backup
[ ] Downloading
[ ] Extracting
[ ] Replace entry points
[ ] Delete old files
[ ] Move new files in place
[ ] Done
```

Continue update? [y/N] █

6. Once all steps are executed the updater will ask you a final question: “Should the “occ upgrade” command be executed?”. This allows you to directly execute the command line based upgrade procedure (occ upgrade). If you select “No” then it will finish with *Please now execute “.occ upgrade” to finish the upgrade..*

Info: Pressing Ctrl-C will finish the currently running step and then stops the updater.

```
[✓] Check for expected files
[✓] Check for write permissions
[✓] Enable maintenance mode
[✓] Create backup
[✓] Downloading
[✓] Extracting
[✓] Replace entry points
[✓] Delete old files
[✓] Move new files in place
[✓] Done
```

Update of code successful.

Should the "occ upgrade" command be executed? [Y/n] █

7. Once the occ upgrade is done you get asked if the maintenance mode should be kept active.

Update of code successful.

```
Should the "occ upgrade" command be executed? [Y/n] y
Nextcloud or one of the apps require upgrade – only a limited number of commands are available
You may use your browser or the occ upgrade command to do the upgrade
Set log level to debug
Updating database schema
Updated database
Updating <federatedfilessharing> ...
Updated <federatedfilessharing> to 1.2.0
Updating <files_pdfviewer> ...
Updated <files_pdfviewer> to 1.1.1
Updated <systemtags> to 1.2.0
Updating <theming> ...
Updated <theming> to 1.3.0
Starting code integrity check...
Finished code integrity check
Update successful
Maintenance mode is kept active
Reset log level
```

Keep maintenance mode active? [y/N] █

13.4.4 Batch mode for command line based updater

It is possible to run the command line based updater in a non-interactive mode. The updater then doesn't ask any interactive questions. It is assumed that if an update is available it should be installed and the `occ upgrade` command is executed as well. After finishing the maintenance mode will be turned off except an error occurred during the `occ upgrade` or the replacement of the code.

To execute this, run the command with the `--no-interaction` option. (i.e. `sudo -u www-data php /var/www/nextcloud/updater/updater.phar --no-interaction`)

```
Nextcloud Updater - version: 1.0.3

Current version is 11.0.3.

Update to Nextcloud 12.0.0 Beta 2 available. (channel: "beta")
Following file will be downloaded automatically: https://download.nextcloud.com/server/prereleases/nextcloud-12.0.0beta2.zip

Updater run in non-interactive mode.

Start update

Info: Pressing Ctrl-C will finish the currently running step and then stops the updater.

[✓] Check for expected files
[✓] Check for write permissions
[✓] Enable maintenance mode
[✓] Create backup
[✓] Downloading
[✓] Extracting
[✓] Replace entry points
[✓] Delete old files
[✓] Move new files in place
[✓] Done

Update of code successful.
Updater run in non-interactive mode - will start "occ upgrade" now.

Nextcloud or one of the apps require upgrade - only a limited number of commands are available
You may use your browser or the occ upgrade command to do the upgrade
Set log level to debug
Updating database schema
Updated database
Updating <federatedfilesharing> ...
Updated <federatedfilesharing> to 1.2.0
Updating <files_pdfviewer> ...
Updated <files_pdfviewer> to 1.1.1
Updating <theming> ...
Updated <theming> to 1.3.0
Starting code integrity check...
Finished code integrity check
Update successful
Maintenance mode is kept active
Reset log level

Updater run in non-interactive mode - will disable maintenance mode now.

Maintenance mode is disabled
```

13.5 Upgrade manually

Always start by making a fresh backup and disabling all 3rd party apps.

1. Back up your existing Nextcloud Server database, data directory, and `config.php` file. (See [Backup](#), for restore information see [Restoring backup](#))
2. Download and unpack the latest Nextcloud Server release (Archive file) from nextcloud.com/install/ into an empty directory outside of your current installation.

Note: To unpack your new tarball, run: `unzip nextcloud-[version].zip` or `tar -xjf nextcloud-[version].tar.bz2`

3. Stop your Web server.
4. In case you are running a cron-job for nextcloud's house-keeping disable it by commenting the entry in the crontab file

```
crontab -u www-data -e
```

(Put a # at the beginning of the corresponding line.)

5. Rename your current Nextcloud directory, for example `nextcloud-old`.
6. Unpacking the new archive creates a new `nextcloud` directory populated with your new server files. Move this directory and its contents to the original location of your old server. For example `/var/www/`, so that once again you have `/var/www/nextcloud`.
7. Copy the `config/config.php` file from your old Nextcloud directory to your new Nextcloud directory.
8. If you keep your `data/` directory in your `nextcloud/` directory, copy it from your old version of Nextcloud to your new `nextcloud/`. If you keep it outside of `nextcloud/` then you don't have to do anything with it, because its location is configured in your original `config.php`, and none of the upgrade steps touch it.
9. If you are using 3rd party application, it may not always be available in your upgraded/new Nextcloud instance. To check this, compare a list of the apps in the new `nextcloud/apps/` folder to a list of the of the apps in your backed-up/old `nextcloud/apps/` folder. If you find 3rd party apps in the old folder that needs to be in the new/upgraded instance, simply copy them over and ensure the permissions are set up as shown below.
10. If you are using 3rd party theme make sure to copy it from your `themes/` directory to your new one. It is possible you will have to make some modifications to it after the upgrade.
11. Adjust file ownership and permissions:

```
chown -R www-data:www-data nextcloud
find nextcloud/ -type d -exec chmod 750 {} \;
find nextcloud/ -type f -exec chmod 640 {} \;
```

12. Restart your Web server.
13. Now launch the upgrade from the command line using `occ`, like this example on Ubuntu Linux:

```
sudo -u www-data php occ upgrade
```

(!) this MUST be executed from within your nextcloud installation directory

14. The upgrade operation takes a few minutes to a few hours, depending on the size of your installation. When it is finished you will see a success message, or an error message that will tell where it went wrong.
15. Reenable the nextcloud cron-job. (See step 4 above.)

```
crontab -u www-data -e
```

(Delete the # at the beginning of the corresponding line in the crontab file.)

Login and take a look at the bottom of your Admin page to verify the version number. Check your other settings to make sure they're correct. Go to the Apps page and review the core apps to make sure the right ones are enabled. Re-enable your third-party apps.

13.5.1 Previous Nextcloud releases

You'll find previous Nextcloud releases in the [Nextcloud Server Changelog](#).

13.5.2 Troubleshooting

Occasionally, *files do not show up after a upgrade*. A rescan of the files can help:

```
sudo -u www-data php console.php files:scan --all
```

See [the nextcloud.com support page](#) for further resources.

Sometimes, Nextcloud can get *stuck in a upgrade* if the web based upgrade process is used. This is usually due to the process taking too long and encountering a PHP time-out. Stop the upgrade process this way:

```
sudo -u www-data php occ maintenance:mode --off
```

Then start the manual process:

```
sudo -u www-data php occ upgrade
```

If this does not work properly, try the repair function:

```
sudo -u www-data php occ maintenance:repair
```

13.6 Upgrade via packages

13.6.1 Upgrade quickstart

One effective, if unofficial method for keeping Nextcloud current on Linux servers is by configuring your system to use Nextcloud via a self contained “Snap” package, A technology allowing users to always have the latest version of an “app”.

That version from Canonical is quite restrictive. It is not aimed at developers or advanced users who would want to tune their configuration by installing extra features. It is aimed at end-users who want a no-brainer solution. Install it, use it. No need to worry about updating Nextcloud any more.

It will work for as long as Canonical pushes releases, just like with any other Linux package maintained independently of Nextcloud.

13.6.2 Installation

Ubuntu \$ sudo snap install nextcloud

All other distros Go to <https://docs.snapcraft.io/installing-snapd/6735> Type the command to install snapd Install Nextcloud \$ sudo snap install nextcloud

13.6.3 1st login

After a successful install, assuming you and the device on which it was installed are on the same network, you should be able to reach the Nextcloud installation by visiting `.local` in your browser. If your hostname is `localhost` or `localhost.localdomain`, like on an Ubuntu Base device (IoT), `nextcloud.local` will be used instead.

You will be asked to create a password for “admin” and your favourite cloud will be ready

Note

Do not use on IoT devices yet. You probably don’t need these instructions anyway if you’re using Snappy Base 16.04 as it’s currently unreleased.


- Make a *fresh backup*.
- Upgrade your Nextcloud snap: `sudo snap refresh nextcloud`
- Run *occ upgrade*.
- Take your Nextcloud server out of *maintenance mode*.
- Re-enable third-party apps.

13.6.4 Upgrade tips

Upgrading Nextcloud from a Snap is just like upgrading any snap package. For example:

```
sudo snap refresh nextcloud
```

Your Snap package manager only upgrades the current Nextcloud Snap. Then your Nextcloud server is immediately put into maintenance mode. You may not see this until you refresh your Nextcloud page.



Then use `occ` to complete the upgrade. You must run `occ` as your HTTP user. This example is for Debian/Ubuntu:

```
sudo -u www-data php occ upgrade
```

This example is for CentOS/RHEL/Fedora:

```
sudo -u apache php occ upgrade
```

13.6.5 Upgrading across skipped releases

It is best to update your Nextcloud installation with every new point release, and to never skip any major releases. While this requirement is being worked on, for the moment If you have skipped any major releases you can bring your Nextcloud current with these steps:

If you are using a Snap package: `sudo snap refresh nextcloud`

If you did **not** install via a Snap package:

1. Upgrade your current version to the latest point release
2. Upgrade your current version to the next major release
3. Run upgrade routine
4. Repeat from step 2 until you reach the last available major release

You'll find previous Nextcloud releases in the [Nextcloud Server Changelog](#).

If upgrading via your Snap package manager fails, then you must perform a *Upgrade manually*.

13.7 Migrating to a different server

If the need arises Nextcloud can be migrated to a different server. A typical use case would be a hardware change or a migration from the virtual Appliance to a physical server. All migrations have to be performed with Nextcloud offline and no accesses being made. Online migration is supported by Nextcloud only when implementing industry standard clustering and HA solutions before Nextcloud is installed for the first time.

To start let us be specific about the use case. A configured Nextcloud instance runs reliably on one machine. For some reason (e.g. more powerful machine is available but a move to a clustered environment not yet needed) the instance needs to be moved to a new machine. Depending on the size of the Nextcloud instance the migration might take several hours. As a prerequisite it is assumed that the end users reach the Nextcloud instance via a virtual hostname (a **CNAME** record in DNS) which can be pointed at the new location. It is also assumed that the authentication method (e.g. LDAP) remains the same after the migration.

Warning: At NO TIME any changes to the **ORIGINAL** system are required **EXCEPT** putting Nextcloud into maintenance mode.

This ensures, should anything unforeseen happen you can go back to your existing installation and provide your users with a running Nextcloud while debugging the problem.

1. Set up the new machine with the desired OS, install and configure the Web server as well as PHP for Nextcloud (e.g. permissions or file upload size limits) and make sure the PHP version matches Nextcloud supported configuration and all relevant PHP extensions are installed. Also set up the database and make sure it is a Nextcloud supported configuration. If your original machine was installed recently just copying that base configuration is a safe best practice.

2. On the original machine then stop Nextcloud. First activate the maintenance mode. After waiting for 6-7 minutes for all sync clients to register the server as in maintenance mode stop the application and/or Web server that serves Nextcloud.
3. Create a dump from the database and copy it to the new machine. There import it in the database (See [Backup](#) and [Restoring backup](#)).
4. Copy all files from your Nextcloud instance, the Nextcloud program files, the data files, the log files and the configuration files, to the new machine (See [Backup](#) and [Restoring backup](#)). The data files should keep their original timestamp (can be done by using `rsync` with `-t` option) otherwise the clients will re-download all the files after the migration. Depending on the original installation method and the OS the files are located in different locations. On the new system make sure to pick the appropriate locations. If you change any paths, make sure to adapt the paths in the Nextcloud config.php file. Note: This step might take several hours, depending on your installation.
5. While still having Nextcloud in maintenance mode (confirm!) and **BEFORE** changing the CNAME record in the DNS start up the database, Web server / application server on the new machine and point your web browser to the migrated Nextcloud instance. Confirm that you see the maintenance mode notice, that a logfile entry is written by both the Web server and Nextcloud and that no error messages occur. Then take Nextcloud out of maintenance mode and repeat. Log in as admin and confirm normal function of Nextcloud.
6. Change the CNAME entry in the DNS to point your users to the new location.

13.8 Migrating from ownCloud

Note: Especially when migrating from ownCloud to Nextcloud you should create a backup of the config, database and the data directory, in case something goes wrong.

Currently migrating from ownCloud is like performing a manual update. So it is quite easy, to migrate from one ownCloud version to at least one Nextcloud version. However this does only work with versions that are close enough database and code-wise. See the table below for a version map, where migrating is easily possible:

ownCloud	Nextcloud
10.0.5 or later	20.0.x (but at least 20.0.5)
10.0.1 - 10.0.5	12.0.x (but at least 12.0.1)
10.0.0	12.0.0
9.1.x	10.0.x
9.0.x	10.0.x
9.0.x	9.0.x

Note: While we understand, that you want to migrate as soon as possible, we also don't want to put your data at risk. Since we never know what ownCloud changes in a future release, we only allow migrations from versions that were released before our last maintenance release, so we can at least perform some basic migration tests, before you migrate your production instance.

1. First download the correct version of Nextcloud from our [older releases](#) page,
2. Make sure to have do a [backup](#) before migrating.
3. Follow the upgrade instructions described in the [Upgrade manually](#) manual.

4. When migrating to Nextcloud 20.0 or later, you will also need to run the following commands after `occ upgrade`:
 - `occ db:convert-filecache-bigint`
 - `occ db:add-missing-columns`
 - `occ db:add-missing-indices`
 - `occ db:add-missing-primary-keys`
5. If system cron was used, please verify if crontab entry was using the command `occ system:cron`. If yes, please adjust it to use the `php` command instead according to [the background jobs configuration documentation](#)
6. Use the [Nextcloud built-in updater](#) to update your instance to the newest version.
7. Make sure to also verify the “Security & setup warnings” in the “Overview” section on the settings page.

ISSUES AND TROUBLESHOOTING

14.1 General troubleshooting

If you have trouble installing, configuring or maintaining Nextcloud, please refer to our community support channels:

- **The Nextcloud Forums** The Nextcloud forums have a [FAQ page](#) where each topic corresponds to typical mistakes or frequently occurring issues

Please understand that all these channels essentially consist of users like you helping each other out. Consider helping others out where you can, to contribute back for the help you get. This is the only way to keep a community like Nextcloud healthy and sustainable!

If you are using Nextcloud in a business or otherwise large scale deployment, note that Nextcloud GmbH offers commercial support options.

14.1.1 Bugs

If you think you have found a bug in Nextcloud, please:

- Search for a solution (see the options above)
- Double-check your configuration

If you can't find a solution, please use our [bugtracker](#). You can generate a configuration report with the `occ config command`, with passwords automatically obscured.

14.1.2 General troubleshooting

Check the Nextcloud [System requirements](#), especially supported browser versions.

When you see warnings about code integrity, refer to [Code signing](#).

Disable 3rdparty / non-shipped apps

It might be possible that 3rd party / non-shipped apps are causing various different issues. Always disable 3rd party apps before upgrades, and for troubleshooting. Please refer to the [Apps commands](#) on how to disable an app from command line.

Nextcloud logfiles

In a standard Nextcloud installation the log level is set to **Normal**. To find any issues you need to raise the log level to **All** in your `config.php` file, or to **Everything** on your Nextcloud Admin page. Please see [Logging](#) for more information on these log levels.

Some logging - for example JavaScript console logging - needs debugging enabled. Edit `config/config.php` and change `'debug' => false`, to `'debug' => true`. Be sure to change it back when you are finished.

For JavaScript issues you will also need to view the javascript console. All major browsers have developer tools for viewing the console, and you usually access them by pressing F12.


Note: The logfile of Nextcloud is located in the data directory `nextcloud/data/nextcloud.log`.

PHP version and information

You will need to know your PHP version and configurations. To do this, create a plain-text file named **phpinfo.php** and place it in your Web root, for example `/var/www/html/phpinfo.php`. (Your Web root may be in a different location; your Linux distribution documentation will tell you where.) This file contains just this line:

```
<?php phpinfo(); ?>
```

Open this file in a Web browser by pointing your browser to `localhost/phpinfo.php`:



Your PHP version is at the top, and the rest of the page contains abundant system information such as active modules, active `.ini` files, and much more. When you are finished reviewing your information you must delete `phpinfo.php`, or move it outside of your Web directory, because it is a security risk to expose such sensitive data.

Debugging sync issues

Warning: The data directory on the server is exclusive to Nextcloud and must not be modified manually.

Disregarding this can lead to unwanted behaviors like:

- Problems with sync clients
- Undetected changes due to caching in the database

If you need to directly upload files from the same server please use a WebDAV command line client like `cadaver` to upload files to the WebDAV interface at:

`https://example.com/nextcloud/remote.php/dav`

Common problems / error messages

Some common problems / error messages found in your logfiles as described above:

- `SQLSTATE[HY000] [1040] Too many connections` -> You need to increase the connection limit of your database, please refer to the manual of your database for more information.
- `SQLSTATE[HY000]: General error: 5 database is locked` -> You're using SQLite which can't handle a lot of parallel requests. Please consider converting to another database like described in [Converting database type](#).
- `SQLSTATE[HY000]: General error: 2006 MySQL server has gone away` -> Please refer to [Troubleshooting](#) for more information.
- `SQLSTATE[HY000] [2002] No such file or directory` -> There is a problem accessing your SQLite database file in your data directory (`data/nextcloud.db`). Please check the permissions of this folder/file or if it exists at all. If you're using MySQL please start your database.
- `Connection closed / Operation cancelled` -> This could be caused by wrong `KeepAlive` settings within your Apache config. Make sure that `KeepAlive` is set to `On` and also try to raise the limits of `KeepAliveTimeout` and `MaxKeepAliveRequests`.
- `No basic authentication headers were found` -> This error is shown in your `data/nextcloud.log` file. Some Apache modules like `mod_fastcgi`, `mod_fcgid` or `mod_proxy_fcgi` are not passing the needed authentication headers to PHP and so the login to Nextcloud via WebDAV, CalDAV and CardDAV clients is failing. Information on how to correctly configure your environment can be found at the [forums](#).

14.1.3 Troubleshooting Web server and PHP problems

Logfiles

When having issues the first step is to check the logfiles provided by PHP, the Web server and Nextcloud itself.

Note: In the following the paths to the logfiles of a default Debian installation running Apache2 with `mod_php` is assumed. On other Web servers, Linux distros or operating systems they can differ.

- The logfile of Apache2 is located in `/var/log/apache2/error.log`.
- The logfile of PHP can be configured in your `/etc/php/7.4/apache2/php.ini`. You need to set the directive `log_errors` to `On` and choose the path to store the logfile in the `error_log` directive. After those changes you need to restart your Web server.
- The logfile of Nextcloud is located in the data directory `/var/www/nextcloud/data/nextcloud.log`.

Web server and PHP modules

Note: Lighttpd is not supported with Nextcloud, and some Nextcloud features may not work at all on Lighttpd.

There are some Web server or PHP modules which are known to cause various problems like broken up-/downloads. The following shows a draft overview of these modules:

1. Apache

- mod_pagespeed
- mod_evasive
- mod_security
- mod_reqtimeout
- mod_deflate
- libapache2-mod-php*filter (use libapache2-mod-php7.4 instead)
- mod_spdy together with libapache2-mod-php5 / mod_php (use fcgi or php-fpm instead)
- mod_dav
- mod_xsendfile / X-Sendfile (causing broken downloads if not configured correctly)

2. NginX

- ngx_pagespeed
- HttpDavModule
- X-Sendfile (causing broken downloads if not configured correctly)

3. PHP

- eAccelerator

14.1.4 Troubleshooting WebDAV

Nextcloud uses SabreDAV, and the SabreDAV documentation is comprehensive and helpful.

See:

- [SabreDAV FAQ](#)
- [Web servers](#) (Lists lighttpd as not recommended)
- [Working with large files](#) (Shows a PHP bug in older SabreDAV versions and information for mod_security problems)
- [0 byte files](#) (Reasons for empty files on the server)
- [Clients](#) (A comprehensive list of WebDAV clients, and possible problems with each one)
- [Finder, OS X's built-in WebDAV client](#) (Describes problems with Finder on various Web servers)

There is also a well maintained FAQ thread available at the [ownCloud Forums](#) which contains various additional information about WebDAV problems.

14.1.5 Service discovery

Some clients - especially on iOS/macOS - have problems finding the proper sync URL, even when explicitly configured to use it.

If you want to use CalDAV or CardDAV clients or other clients that require service discovery together with Nextcloud it is important to have a correct working setup of the following URLs:

`https://example.com/.well-known/carddav`

`https://example.com/.well-known/caldav`

Those need to be redirecting your clients to the correct endpoints. If Nextcloud is running at the document root of your Web server the correct URL is `https://example.com/remote.php/dav` for CardDAV and CalDAV and if running in a subfolder like `nextcloud`, then `https://example.com/nextcloud/remote.php/dav`.

For the first case the `.htaccess` file shipped with Nextcloud should do this work for you when you're running Apache. You need to make sure that your Web server is using this file. Additionally, you need the `mod_rewrite` Apache module installed to process these redirects. When running Nginx please refer to [NGINX configuration](#).

If your Nextcloud instance is installed in a subfolder called `nextcloud` and you're running Apache create or edit the `.htaccess` file within the document root of your Web server and add the following lines:

```
<IfModule mod_rewrite.c>
RewriteEngine on
RewriteRule ^\.well-known/carddav /nextcloud/remote.php/dav [R=301,L]
RewriteRule ^\.well-known/caldav /nextcloud/remote.php/dav [R=301,L]
RewriteRule ^\.well-known/webfinger /nextcloud/index.php/.well-known/webfinger [R=301,
↪L]
RewriteRule ^\.well-known/nodeinfo /nextcloud/index.php/.well-known/nodeinfo [R=301,L]
</IfModule>
```

Make sure to change `/nextcloud` to the actual subfolder your Nextcloud instance is running in.

If you are running NGINX, make sure `location = /.well-known/carddav {` and `location = /.well-known/caldav {` are properly configured as described in [NGINX configuration](#), adapt to use a subfolder if necessary.

Now change the URL in the client settings to just use:

`https://example.com`

instead of e.g.

`https://example.com/nextcloud/remote.php/dav/principals/username`.

There are also several techniques to remedy this, which are described extensively at the [Sabre DAV website](#).

14.1.6 Troubleshooting sharing

Users' Federated Cloud IDs not updated after a domain name change

1. run Database query

```
DELETE FROM oc_cards_properties WHERE name = 'CLOUD' AND addressbookid = (select id from oc_addressbooks where principaluri = 'principals/system/system' AND uri = 'system');
```

2. run occ commands

```
occ dav:sync-system-addressbook
occ federation:sync-addressbooks
```

14.1.7 Troubleshooting contacts & calendar

Unable to update contacts or events

If you get an error like:

```
PATCH https://example.com/remote.php/dav HTTP/1.0 501 Not Implemented
```

it is likely caused by one of the following reasons:

Using Pound reverse-proxy/load balancer As of writing this Pound doesn't support the HTTP/1.1 verb. Pound is easily [patched](#) to support HTTP/1.1.

Misconfigured Web server Your Web server is misconfigured and blocks the needed DAV methods. Please refer to [Troubleshooting WebDAV](#) above for troubleshooting steps.

14.1.8 Troubleshooting data-directory

If you have a fresh install, consider reinstalling with your preferred directory location.

Unofficially moving the data directory can be done as follows:

1. Make sure no cron jobs are running
2. Stop apache
3. Move /data to the new location
4. Change the config.php entry
5. Edit the database: In oc_storages change the path on the local::/old-data-dir/ entry
6. Ensure permissions are still correct
7. Restart apache

For a safe moving of data directory, supported by Nextcloud, recommended actions are:

1. Make sure no cron jobs are running
2. Stop apache
3. Move /data to the new location

4. Create a symlink from the original location to the new location
5. Ensure permissions are still correct
6. Restart apache

14.1.9 Troubleshooting encryption

Problems when downloading or decrypting files

In some rare cases it can happen that encrypted files cannot be downloaded and return a “500 Internal Server Error”. If the Nextcloud log contains an error about “Bad Signature”, then the following command can be used to repair affected files:

```
occ encryption:fix-encrypted-version userId --path=/path/to/broken/file.txt
```

Replace “userId” and the path accordingly. The command will do a test decryption for all files and automatically repair the ones with a signature error.

14.1.10 Other issues

Some services like *Cloudflare* can cause issues by minimizing JavaScript and loading it only when needed. When having issues like a not working login button or creating new users make sure to disable such services first.

14.2 Code signing

Nextcloud supports code signing for the core releases, and for Nextcloud applications. Code signing gives our users an additional layer of security by ensuring that nobody other than authorized persons can push updates.

It also ensures that all upgrades have been executed properly, so that no files are left behind, and all old files are properly replaced. In the past, invalid updates were a significant source of errors when updating Nextcloud.

14.2.1 FAQ

Why did Nextcloud add code signing?

By supporting Code Signing we add another layer of security by ensuring that nobody other than authorized persons can push updates for applications, and ensuring proper upgrades.

Do we lock down Nextcloud?

The Nextcloud project is open source and always will be. We do not want to make it more difficult for our users to run Nextcloud. Any code signing errors on upgrades will not prevent Nextcloud from running, but will display a warning on the Admin page. For applications that are not tagged “Official” the code signing process is optional.

Not open source anymore?

The Nextcloud project is open source and always will be. The code signing process is optional, though highly recommended. The code check for the core parts of Nextcloud is enabled when the Nextcloud release version branch has been set to stable.

For custom distributions of Nextcloud it is recommended to change the release version branch in version.php to something else than “stable”.

Is code signing mandatory for apps?

Code signing is required for all applications on apps.nextcloud.com.

14.2.2 Fixing invalid code integrity messages

A code integrity error message (“Some files have not passed the integrity check...”) appears on your Nextcloud admin page under “Overview”, which provides the following options:

1. Link to this documentation entry.
2. Show a list of invalid files.
3. Trigger a rescan.

Security & setup warnings ⓘ

It's important for the security and performance of your instance that everything is configured correctly. To help you with that we are doing some automatic checks. Please see the linked documentation for more information.



There are some errors regarding your setup.

- Some files have not passed the integrity check. Further information on how to resolve this issue can be found in the [documentation](#). ([List of invalid files...](#) / [Rescan...](#))

To debug issues caused by the code integrity check click on “List of invalid files..”, and you will be shown a text document listing the different issues. The content of the file will look similar to the following example:

Technical information

=====

The following **list** covers which files have failed the integrity check. Please read the previous linked documentation to learn more about the errors **and** how to fix them.

Results

=====

- core
 - INVALID_HASH
 - /index.php
 - /version.php
 - EXTRA_FILE
 - /test.php
- calendar
 - EXCEPTION

(continues on next page)

(continued from previous page)

- OC\IntegrityCheck\Exceptions\InvalidSignatureException
- Signature data **not** found.

Raw output

=====

Array

```
(
  [core] => Array
    (
      [INVALID_HASH] => Array
        (
          [/index.php] => Array
            (
              [expected] =>
                f1c5e2630d784bc9cb02d5a28f55d6f24d06dae2a0fee685f3
                c2521b050955d9d452769f61454c9ddfa9c308146ade10546c
                fa829794448eaffbc9a04a29d216
              [current] =>
                ce08bf30bcb879a18b49239a9bec6b8702f52452f88a9d321
                42cad8d2494d5735e6bfa0d8642b2762c62ca5be49f9bf4ec2
                31d4a230559d4f3e2c471d3ea094
            )
          [/version.php] => Array
            (
              [expected] =>
                c5a03bacae8dedf8b239997901ba1fffd2fe51271d13a00cc4
                b34b09cca5176397a89fc27381cbb1f72855fa18b69b6f87d7
                d5685c3b45aee373b09be54742ea
              [current] =>
                88a3a92c11db91dec1ac3be0e1c87f862c95ba6ffaaaa3f2c3
                b8f682187c66f07af3a3b557a868342ef4a271218fe1c1e300
                c478e6c156c5955ed53c40d06585
            )
          )
        [EXTRA_FILE] => Array
          (
            [/test.php] => Array
              (
                [expected] =>
                [current] =>
                09563164f9904a837f9ca0b5f626db56c838e5098e0ccc1d8b
                935f68fa03a25c5ec6f6b2d9e44a868e8b85764dafd1605522
                b4af8db0ae269d73432e9a01e63a
              )
            )
          )
    )
)
```

(continues on next page)

(continued from previous page)

```
[calendar] => Array
(
    [EXCEPTION] => Array
        (
            [class] => OC\IntegrityCheck\Exceptions\InvalidSignature
            Exception
            [message] => Signature data not found.
        )
    )
)
```

In above error output it can be seen that:

1. In the Nextcloud core (that is, the Nextcloud server itself) the files “index.php” and “version.php” do have the wrong version.
2. In the Nextcloud core the unrequired extra file “/test.php” has been found.
3. It was not possible to verify the signature of the calendar application.

The solution is to upload the correct “index.php” and “version.php” files, and delete the “test.php” file. For the calendar exception contact the developer of the application. For other means on how to receive support please take a look at <https://nextcloud.com/support/>. After fixing these problems verify by clicking “Rescan...”.

Note: When using a FTP client to upload those files make sure it is using the Binary transfer mode instead of the ASCII transfer mode.

14.2.3 Rescans

Rescans are triggered at installation, and by updates. You may run scans manually with the occ command. The first command scans the Nextcloud server files, and the second command scans the named app. There is not yet a command to manually scan all apps:

```
occ integrity:check-core
occ integrity:check-app $appid
```

See *Using the occ command* to learn more about using occ.

14.2.4 Errors

Warning: Please don't modify the mentioned `signature.json` itself.

The following errors can be encountered when trying to verify a code signature.

- `INVALID_HASH`
 - The file has a different hash than specified within `signature.json`. This usually happens when the file has been modified after writing the signature data.

- **MISSING_FILE**
 - The file cannot be found but has been specified within `signature.json`. Either a required file has been left out, or `signature.json` needs to be edited.
- **EXTRA_FILE**
 - The file does not exist in `signature.json`. This usually happens when a file has been removed and `signature.json` has not been updated. It also happens if you have placed additional files in your Nextcloud installation folder.
- **EXCEPTION**
 - Another exception has prevented the code verification. There are currently these following exceptions:
 - * **Signature data not found.**
 - The app has mandatory code signing enforced but no `signature.json` file has been found in its `appinfo` folder.
 - * **Certificate is not valid.**
 - The certificate has not been issued by the official Nextcloud Code Signing Root Authority.
 - * **Certificate is not valid for required scope. (Requested: %s, current: %s)**
 - The certificate is not valid for the defined application. Certificates are only valid for the defined app identifier and cannot be used for others.
 - * **Signature could not get verified.**
 - There was a problem with verifying the signature of `signature.json`.

15.1 Cookies

Nextcloud only stores cookies needed for Nextcloud to work properly. All cookies comes from your Nextcloud server directly, no 3rd-party cookies will be sent to your system. Regarding GDPR, [only data which contain personal data are relevant](#).

15.1.1 Cookies stored by Nextcloud

Cookie	Data Stored	Lifetime
Session cookie	• session ID • secret token (used to decrypt the session on the server)	24 minutes
Same-site cookies	no user-related data are stored, all same-site cookies are the same for all users on all Nextcloud instances	forever
Remember-me cookie	• user id • original session id • remember token	15 days (can be configured)

The same-site cookies are used to determine how a request reaches the Nextcloud server. We use them to prevent CSRF attacks. No identifiable information is stored in those. The rest of the cookies are strictly used to identify the user to the system.